

How to Configure IPsec or PPTP on Mobile Devices

https://campus.barracuda.com/doc/39815525/

To configure your mobile device to connect to the Barracuda SSL VPN, follow the instructions given in the relevant article section:

Configure an iOS device

The Barracuda SSL VPN will automatically make the configuration changes required on your iPhone or iPad. To configure the client device, complete the following steps:

- 1. In Safari, go to the login page of the Barracuda SSL VPN; for example: https://sslvpn.example.com/.
- 2. Go to **My Options > Settings > Custom Device Setup**. You will see a **Setup VPN** button if the Barracuda SSL VPN is configured to accept L2TP/IPsec connections.
- 3. Tap the **Setup VPN** button. This will launch a mobile configuration profile that will prompt you to install it.
- 4. Select **Install**, and then select **Install Now**.
- 5. Enter your account name and password and click **Next**.
- 6. Click **Done**. The newly-created connection will appear in the **VPN** menu as well as in the main **Settings** menu.
- 7. Go to **Settings > General > Network > VPN > < VPN name>** to start the connection.

Configure an Android device

To configure your Android device to connect to the Barracuda SSL VPN, complete the following steps:

- 1. On the Android device, tap **Settings > Wireless & Networks > VPN Settings > Add VPN**.
- 2. To configure an **L2TP/IPsec** connection, select **Add L2TP/IPsec PSK VPN** (for Preshared key) and configure only the following settings (for all other settings, accept the default values):
 - **VPN name** A name for this connection (for example: *Sslvpn-ipsec*).
 - Set VPN server The hostname or IP address of the Barracuda SSL VPN (for example: sslvpn.example.com).
 - **Set IPsec pre-shared key** Select to enter the pre-shared key.
 - **Enable L2TP secret** Clear this setting.
 - **DNS search domains** Enter the default domain for the protected network (for example: *example.com*).
- 3. To configure a **PPTP** connection, select **Add PPTP VPN** and configure only the following



settings (for all other settings, accept the default values):

- **VPN name** A name for this connection; for example: *Sslvpn-pptp*.
- Set VPN server The hostname or IP address of the Barracuda SSL VPN (for example: sslvpn.example.com).
- **Enable Encryption** Select to enable encryption of your PPTP session.
- DNS search domains Enter the default domain for the protected network (for example: example.com).
- 4. Select **Save**. The newly-created connection appears in the **VPN Settings** menu.

When you attempt a connection to the Barracuda SSL VPN, you are prompted for your username and password.

Configure a Windows 8 RT surface tablet

Edit Windows 8 RT registry entry

If both your remote computer and the Barracuda SSL VPN are behind a router that uses NAT (which is the most common scenario), you will have to edit the Windows 8 RT registry to allow access to an L2TP/IPsec server behind NAT-T devices.

To edit the registry entry on Windows RT, proceed as follows:

- 1. On the Microsoft Surface tablet, swipe in from the right edge of the screen, and tap the **Search** (magnifying glass) charm.
- 2. Type **regedit** and select it from the list.
- 3. Navigate
 - to Computer\HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\PolicyAgent.
- 4. On the Edit menu, point to New, and then click DWORD (32-bit) Value.
- 5. Type AssumeUDPEncapsulationContextOnSendRule, and then press Enter.
- 6. Right-click AssumeUDPEncapsulationContextOnSendRule, and then click Modify.
- 7. In the **Value Data** box, set the value to 2.
- 8. Click **OK** and exit regedit.
- 9. Restart Windows 8 RT:
 - 1. Swipe in from the right edge of the screen, and tap **Settings**.
 - 2. Tap or click **Power**, and then tap or click **Restart**.

Create the IPsec connection

Use the following steps to create the IPsec connection:

- 1. On the Microsoft Surface tablet, swipe in from the right edge of the screen, and tap the **Search** (magnifying glass) charm.
- 2. Type **VPN** to search for it in settings.



- 3. Select **Set up a virtual private network (VPN) connection.** This opens the **Create a VPN Connection** window in Desktop mode.
- 4. Enter the Barracuda SSL VPN IP address or host name, and enter a name for the connection.
- 5. Click **Create**. The Networks widget will appear and give you the option to connect. This is not going to work yet though as you have not yet entered the preshared Key. Press the icon to the right of the new connection until the **Context** menu appears.
- 6. Select **View Connection Properties**. The **Properties** will display in desktop mode.
- 7. Click the **Security** tab, and set the VPN type to **Layer 2 Tunneling Protocol with IPsec** (L2TP/IPsec).
- 8. Click **Advanced Settings**. Select **Use pre-shared key for authentication**, and enter the preshared key that your administrator gave to you and click **OK**.
- 9. On the **Security** tab:
 - 1. Select Allow these protocols
 - 2. Select PAP
 - 3. Clear MS-CHAP v2 (so only PAP is selected)
 - 4. Click OK.

Launch SSL VPN

Use the following steps to launch SSL VPN:

- 1. On the Microsoft Surface tablet, swipe in from the right edge of the screen, tap the **Settings** (gear) charm, and then tap the currently connected network icon. The **Networks** list will display, and you will see the IPsec connection near the top.
- 2. Select that connection. Tap **Connect**. Enter your login credentials to access the Barracuda SSL VPN.

Configure a Windows mobile device

If you own a device running Windows Mobile complete the following steps:

- On the Windows Mobile device, navigate to: Settings > Connections > Add a new VPN server connection.
- 2. Select **Make New Connection**, and then configure just the following (for all other settings, accept the default values):
 - Name A name for this connection; for example: Sslvpn-pptp
 - Hostname/IP The FQDN or IP address of the Barracuda SSL VPN; for example: sslvpn.example.com
 - **VPN type** Select the desired VPN type (**IPSec/L2TP** or **PPTP**).
- 3. Select **Next**.
- 4. If **IPsec/L2TP** was chosen, then a screen will appear from which you must select **A pre-shared key** and enter the PSK for the Barracuda SSL VPN.
- 5. Then, select **Next**. The newly-created connection will appear in the **Connections** page, in

Barracuda SSL VPN



the **VPN** tab.

Your username and password will be requested when a connection to the Barracuda SSL $\ensuremath{\mathsf{VPN}}$ is attempted.

Barracuda SSL VPN



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.