

## Example - How to Enable Remote Management Access From the Internet

<https://campus.barracuda.com/doc/41116260/>


Barracuda Networks recommends that you only enable management access from the Internet for a limited period of time. Remote management access constitutes a significant security risk, especially if you allow access via SSH. To minimize risk potential, restrict access to very few trusted source addresses or networks, disable access when it is not needed, and use strong passwords or key authentication.

When you place a standalone Barracuda NG Firewall at a remote site, you can enable access to it over the Internet for remote management and configuration. You can also enable remote access for Barracuda Networks Technical Support if direct access to the system is required for troubleshooting.

### Create an App Redirect Firewall Rule

To enable remote management access to the Barracuda NG Firewall from the Internet, create an [App Redirect Rule](#) for the management ports to the internal management IP address.

1. Open the **Forwarding Rules** page (**Config > Full Config > Box > Virtual Servers > your virtual server > Assigned Services > Firewall > Forwarding Rules**).
2. From the **Rule Lists** menu in the left pane, select **Access Rules**.
3. Click **Lock**.
4. Create an **App Redirect** rule with the following settings:
  - **Source** - Select **Internet**. To restrict access to specific IP addresses, you can explicitly enter the IP addresses or [create a network object](#) for reference.
  - **Service** - Select **NGF-MGMT-STAT** (TCP 807 Single Point Of Entry)
  - **Destination** - If the Barracuda NG Firewall connects to the Internet via a dynamic address, select the network object to match your connection (**DHCP Local IP, DSL Local IP or 3G Local IP**). If the system uses a static public IP address, enter this address.
  - **Redirection** - In the **Local Address** field, enter your internal management IP address (MIP) as defined in the network settings.



5. Click **Send Changes** and **Activate**.

## Next Step

You can now manage your Barracuda NG Firewall over the Internet with the Barracuda NG Admin application. Instead of connecting to the management IP address of the unit, log into the system via the public IP address of your unit.

## Figures

### 1. RemoteManagementFWRule01.png

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.