

How to Configure an Outlook Web Access Web Forward


<https://campus.barracuda.com/doc/46209060/>

The Barracuda NextGen Firewall F-Series SSL VPN offers preconfigured web forward templates for Outlook Web Access 2003, 2007, and 2010. By default the session username and password is used to authenticate on the Outlook Web Access portal. If the user must use a different password or user to sign in, create user attributes to replace the session attributes.

In this article

Configure an Outlook Web Access Web Forward (OWA)

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > VPN-Service > SSL-VPN**.
2. In the left menu, select **Web Forwards**.
3. Click **Lock**.
4. Click **+** to add a web forward to the **Web Forwards** list. The **Web Forwards List** opens.
5. Select **OWA** template matching your Exchange server from the **Web Resource Template** dropdown. The **Enter Name** window opens.




Web Resource Access Authorization

Active

Web Resource Template OWA_2003

6. Enter the hostname of your Microsoft Exchange server and click **OK**.




Enter Name

What is the hostname of the exchange server?

mail.yourdomain.com

OK Cancel

7. (OWA 2003 only) Enter the Single Sign On (SSO) domain for your Exchange server and click **OK**.



8. Enter the **Visible Name**. This is the name used in the desktop and mobile portal for this web forward.
9. (optional) Enter a **Link Description** in HTML. The link description is not displayed in the mobile portal.
10. (optional) Check **Must be Healthy** if the user has to pass a health check before launching the forward. This setting requires a configured NAC client on a Windows device and policy server. For more information, see [Access Control Service](#).
11. (optional) To restrict access to the web forward by user group, replace the * entry in the **Allowed User Groups** list. Click + to add new user group.
12. (optional) Click **Ex/Import** to upload a custom icon.
13. (optional) To use user attributes to sign in, replace the session attributes in the username and password entries with user attributes. For more information on how to create user attributes, see [How to Use and Create Attributes](#).
14. Click **OK**.
15. Click **Send Changes** and **Activate**.

Figures

1. owa01.png
2. owa02.png
3. owa03.png

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.