

conftool

<https://campus.barracuda.com/doc/48203206/>

To rebuild database files or the entire configuration tree, use the *conftool* utility. You can use *conftool* either for a single Barracuda NextGen Firewall F-Series configuration or for a Barracuda NextGen Control Center range configuration. Rebuilding the configuration tree might be necessary if it shows inconsistent entries, such as when Mail Gateway configuration objects suddenly appear in the Firewall configuration section. Such an error is usually caused by invalid, corrupt, or inconsistent database files.

Commands for a Barracuda NextGen Firewall F-Series

To rebuild the configuration tree for a Barracuda NextGen Firewall F-Series, use the following syntax:

conftool b [cmd]

The following table lists the various commands that you can use for a Barracuda NextGen Firewall F-Series:

Command	Description
<i>conftool b help</i>	Displays all options available with <i>conftool</i> .
<i>conftool b rebuild_cache</i>	Performs a complete rebuild of the tree cache.
<i>conftool b rebuild_db</i>	Performs a complete rebuild of the database files.

Commands for a Barracuda NextGen Control Center

To rebuild the configuration tree for a Barracuda NextGen Control Center range, use the following syntax:

conftool [rmc] [server_service] [cmd]

The following table lists the various commands that you can use for a Barracuda NextGen Control Center range:

Command	Description
<i>conftool r</i>	Performs a complete rebuild of the configuration tree for the range.

<i>conftool m</i>	Performs a complete rebuild of the configuration tree for multiple clusters.
<i>conftool c</i>	Performs a complete rebuild of the configuration tree for a single cluster.
<i>conftool par <range>_<cluster>
<target directory></i>	Creates PAR files for the specified Barracuda NextGen Control Center ranges and clusters.

Usage Examples

The following table lists usage examples for ***conftool*** :

Task	Command
To rebuild the Barracuda NextGen Firewall F-Series configuration database files on the executing box.	<i>conftool b rebuild_db</i>
To rebuild the range configuration tree cache of the Config service on the main server. The main server must be a Barracuda NextGen Control Center server and the config service must be a rangeconf service.	<i>conftool r main_config rebuild_cache</i>
To rebuild the reference database (<i>noderef.db</i>) without updating the firewall rulesets (<i>norule</i>). The <i>nosend</i> argument prevents config updates from being sent to the Barracuda NextGen Firewall F-Series.	<i>conftool r - activate nosend norule</i> Only execute this command when advised to do so by Barracuda Networks Technical Support .

© Barracuda Networks Inc., 2021 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.