

How to Deploy the Barracuda WAF Control Center Vx image

https://campus.barracuda.com/doc/54264433/

Barracuda Networks offers the following types of images for the Barracuda WAF Control Center (WCC) Vx deployment. Follow the instructions for your hypervisor to deploy the Barracuda WAF Control Center Vx appliance.

Image Type	Supported Hypervisors
OVF	 VMware ESX and ESXi (vSphere Hypervisor) versions 4.x VMware ESX and ESXi (vSphere Hypervisor) versions 5.x and 6.x Sun/Oracle VirtualBox and VirtualBox OSE version 3.2
VMX	VMware Server 2.xVMware Workstation 6.x, Player 3.x, and Fusion 3.x
XVA	Citrix XenServer 5.5+
VHD	 Microsoft Hyper-V 2008 Microsoft Hyper-V 8, 8.1, 2012, 2012 R2, 10

You can download these images from the <u>Barracuda Virtual Appliance Download page</u>. After the download is complete, extract the files from the ZIP folder.

Deploy OVF Images

VMware ESX and ESXi 4.x

Use the OVF file ending in -4x. ovf for this hypervisor.

- 1. Download and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. From the **File** menu in the vSphere Client, select **Deploy OVF Template**.
- Select Import from file, navigate to the extracted folder, and locate the Barracuda WAF Control Center Vx OVF file. Click Next.
- 4. Set the network to point to the target network for this virtual appliance.
- 5. Follow the recommendations in Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx.
- 6. Right-click your virtual appliance, select **Open Console**, and click the green arrow to power it
- 7. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to provision your virtual appliance.

VMware ESX, ESXi 5.x, and ESXi 6.x

Use the OVF file ending in -5x.ovf for the ESXi 5.x hypervisor and use the OVF file ending in -6x.ovf



for the ESXi 6.x hypervisor.

- 1. <u>Download</u> and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. Launch vSphere Client and select the appropriate resource pool.
- 3. From the File menu in the vSphere Client, select Deploy OVF Template.
- 4. Click **Browse**, navigate to the extracted folder, and locate the Barracuda WAF Control Center Vx OVF file.
- 5. Click **Next**. Verify that you are installing the correct Barracuda virtual appliance. Click **Next** again.
- 6. Enter a name for the virtual appliance. Click **Next**.
- 7. Select the destination storage for the virtual machine. Click **Next**.
- 8. Select a disk format. To ensure maximum stability when deploying your Barracuda Vx appliance, specify the disk format as **Thick Provision Eager Zeroed**. Click **Next** .
- 9. Map the network to the target network for this virtual appliance. Click **Next**.
- 10. Review the deployment options. Click **Finish** to deploy the virtual appliance.
- 11. Click **Finish** to deploy the appliance.
- 12. Follow the recommendations in **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**.
- 13. Locate the appliance within the appropriate virtual machine and resource pool. Select it and power it on by clicking the green arrow.
- 14. Click the **Console** tab. You can monitor the appliance as it is prepared for use.
- 15. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to set up your virtual appliance.

Sun/Oracle VirtualBox and VirtualBox OSE 3.2

Use the OVF file ending in -4x. ovf for this hypervisor.

- 1. Download and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. From the **File** menu in the VirtualBox client, select **Import Appliance**.
- 3. Navigate to the extracted folder and locate the Barracuda WAF Control Center Vx OVF file.
- 4. Select the file and click **Next**.
- 5. On the **Import Settings** screen, follow the recommendations in **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**. Click **Finish**.
- 6. Start the appliance.
- Follow the Barracuda WAF Control Center Vx Quick Start Guide instructions to set up your virtual appliance.

Deploy VMX Images

VMware Server 2.x

Use the .vmx and .vmdk files for this hypervisor .



- 1. <u>Download</u> and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. Navigate to the extracted folder and move the files ending in .vmx and .vmdk into a folder in your datastore (which you can locate from the **Datastores** list on your server's summary page).
- 3. From the VMware Infrastructure Web Access client's **Virtual Machine** menu, select **Add Virtual Machine to Inventory**.
- 4. Navigate to the folder in your datastore used in step 2 and select the file ending in .vmx. Click OK.
- 5. Follow the recommendations in Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx.
- 6. Start the appliance.
- 7. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to set up your virtual appliance.

VMware Workstation 6.x, Player 3.x, and Fusion 3.x

Use the .vmx file for this hypervisor .

- 1. <u>Download</u> and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. From the File menu, select Open a Virtual Machine.
- 3. Navigate to the extracted folder and select the file ending in .vmx.
- 4. Use the default settings and click Finish.
- 5. Follow the recommendations in Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx.
- 6. Start the appliance.
- 7. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to set up your virtual appliance.

Deploy XVA Images

Citrix XEN Server 5.5+

Use the .xva file for this hypervisor. For XEN Server, you first import the virtual appliance template and then create a new virtual appliance based on that template.

Step 1. Import the virtual appliance template:

- 1. <u>Download</u> and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. From the **File** menu in the XenCenter client, select **Import**.
- 3. Click **Browse**, navigate to the extracted folder, and select the file ending in .xva. Click **Next**.
- 4. Select a server for the template. Click **Next**.
- 5. Select a storage repository for the template. Click **Import**.
- 6. Select a virtual network interface for the template. Click **Next**.
- 7. Review the template settings. Click **Finish** to import the template.



Step 2. Create a new virtual appliance:

- 1. Right-click the virtual appliance template and select **New VM wizard**.
- 2. Select the virtual appliance template. Click **Next**.
- 3. Enter a name for the virtual appliance. Click **Next**.
- 4. For the DVD drive, select . Click Next.
- 5. Select a home server. Click **Next**.
- 6. Specify the number of virtual CPUs and memory for the virtual appliance. Follow the recommendations in **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**. Click **Next**.
- 7. Select a virtual disk. Click Next.
- 8. Select a virtual network interface. Click **Next**.
- 9. Review the virtual appliance settings. Click **Create Now**.
- 10. When the virtual appliance is ready, right-click it and then click **Start**.
- 11. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to set up your virtual appliance.

Deploy VHD Images

Microsoft Hyper-V 2008

Use the **.vhd** file for this hypervisor.

- 1. <u>Download</u> and expand the Barracuda WAF Control Center Vx ZIP folder.
- 2. Navigate to the extracted folder and verify that the **HyperV** folder contains the following subfolders:
 - Snapshots
 - Virtual Hard Disks
 - Virtual Machines
- 3. In Hyper-V Manager, right-click the VM host and select **Import Virtual Machine**.
- 4. Navigate to the extracted folder, select the **HyperV** folder, and click **Select Folder**.
- 5. Select Copy the virtual machine and Duplicate all files. Click Import.
- 6. Follow the recommendations in **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**.
- 7. Start the Barracuda WAF Control Center Vx by right-clicking the virtual machine and selecting **Start**.
- Follow the Barracuda WAF Control Center Vx Quick Start Guide instructions to set up your virtual appliance.

Microsoft Hyper-V 8, 8.1, 2012, 2012 R2, and 10

Use the .vhd file for this hypervisor.

1. Download and expand the Barracuda WAF Control Center Vx ZIP folder.



- 2. Launch the *WinServerSetup.bat* file located in the extracted folder. This batch file corrects a compatibility issue and takes less than a minute to run.
- 3. Navigate to the extracted folder and verify that the **HyperV** folder contains the following subfolders:
 - Snapshots
 - Virtual Hard Disks
 - Virtual Machines
- 4. In Hyper-V Manager, right-click the VM host and select **Import Virtual Machine**.
- 5. On the **Before You Begin** page of the **Import Virtual Machine** wizard, click **Next**.
- 6. On the **Locate Folder** page:
 - Click Browse, navigate to the extracted folder, and select the HyperV folder. Click Select Folder.
 - 2. Click Next.
- 7. On the **Select Virtual Machine** page, click **Next**.
- 8. On the Choose Import Type page, select Copy the virtual machine (created a new unique ID). Click Next.
- 9. On the **Choose Destination: Choose Folders for Virtual Machine Files** page, click **Browse** to search for the location where you want to store the VM files. Click **Next**.
- On the Choose Storage Folders: Choose Folders to Store Virtual Hard Disks page, click Browse to search for the location where you want to store the virtual hard disks for the VM. Click Next.
- 11. For Microsoft Windows 10, you can modify the RAM and Hard Disk space allocations after completing step **12**.
 - On the **Configure Memory** page, enter a size for the **Startup RAM** that meets the requirements at **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**. Keep the default settings for the other fields. Click **Next.**
- 12. On the **Connect Network** page, select the network interface that you want to use for management access of the VM. Click **Next**.
- 13. On the **Summary** page, verify that all the settings are correct. Click **Finish**.
- 14. For Microsoft Windows 10, go to the **Actions** pane and click on **Settings** under **Barracuda WAF Control Center**. Under Hardware, ensure that their is enough memory and hard disk space as specified in **Allocating Cores, RAM, and Hard Disk Space for Your Barracuda WAF Control Center Vx**.
- 15. Start your virtual appliance.
- 16. Follow the **Barracuda WAF Control Center Vx Quick Start Guide** instructions to set up your virtual appliance.

To take advantage of Microsoft's VHDX support on Hyper-V 2012, 2012 R2 and 10, follow the instructions in <u>How to Convert and Replace a Barracuda Virtual Appliance VHD File with a VHDX Format File.</u>

Barracuda WAF Control Center



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.