

## Cloud LiveBoot Virtual Machine Recovery

<https://campus.barracuda.com/doc/78809480/>

Cloud LiveBoot allows you to boot VMware and Hyper-V virtual machines (VMs) in the Barracuda Cloud for testing, recovery verification, and file-based recovery.

Cloud LiveBoot is available to all Barracuda Backup customers with an Instant Replacement and Barracuda Cloud Storage subscription and is available to all customers excluding those in Japan.

Once VMs are booted in the Barracuda Cloud, you can connect to them by using the VNC client of your choice. Barracuda provides you with a unique IP address and password for each VM. VMs running in the Barracuda Cloud remain operational for seven days before they are shut down and permanently deleted. If you require additional time, contact [Barracuda Networks Technical Support](#).

The number of VMs that you can run in the Barracuda Cloud at once is based on the Barracuda Backup model, as shown in Table 1.

**Table 1. Virtual Images by Model**

Barracuda Backup Model	Maximum Number of Running VMs
190/290/390	1
490/690/6090	3
790/791	4
890/891/895/8090/990/991/995/9090/1090/1091/10090	5

In addition to the limits on number of VMs that can be run at once in the Barracuda Cloud, there are also limits on the size of the VM that can be booted in the Barracuda Cloud, as shown in Table 2.

**Table 2. Cloud LiveBoot Supported Limits**

Maximum vCPU Cores	Maximum RAM	Maximum VM Size	Maximum Number of Disks
8	16 GB	2.5 TB	4

To use Cloud LiveBoot to recover a VM in the Barracuda Cloud:

1. Log into the Barracuda Backup cloud interface.
2. Go to the **Restore > Cloud LiveBoot** page.
3. Click **Add VM** to display up the VM selection dialog box.
4. Select the VMs you want to add to the Cloud LiveBoot page for recovery:

## Add VMs for Cloud LiveBoot ✕

There are **12 VMs** available for selection.

Filter

VM Name	Platform	Data Source
<input type="checkbox"/> ACTIVEDIRECTORY-CAM	VMWare	10.143.240.10
<input type="checkbox"/> EXCHANGE-CAM	VMWare	10.143.240.10
<input type="checkbox"/> FILESERVER-ARB	VMWare	10.143.240.10
<input type="checkbox"/> FREENAS-CAM	VMWare	10.143.240.10
<input type="checkbox"/> Host Component	Hyper-V	HYPERV.C...

[Show 5 more VMs](#)

[Add](#)

5. Click **Add**.
6. In the **Revision** column, select which backup revision you want to recover for each VM. The latest revision is always selected by default.
7. Once you are ready to boot a VM in the Barracuda Cloud, click **Start**:

BU Dashboard Backup Restore Reports System Admin


Restore Browser LiveBoot Cloud LiveBoot
Add VM

**Cloud LiveBoot** Available Cloud LiveBoot Instances ∞ out of ∞

VM Name	Status	Platform	Data Source	Revision	VNC	Interface Type	Actions
<input type="checkbox"/> FILESERVER-ARB 600 GB	Not Running	VMWare	10.143.240.10	08/30/2018			Start Remove
<input type="checkbox"/> ACTIVEDIRECTORY-CAM 100 GB	Not Running	VMWare	10.143.240.10	08/30/2018			Start Remove

8. Once the VM **Status** changes to **Running**, you can click the **Live Preview** link in the VNC column to watch the boot progress:

### VM Preview: FILESERVER-ARB ✕



**How to connect to VM**

1. Install a VNC Client ([RealVNC](#), [TightVNC](#), etc) to your computer.
2. Enter the IP address and port number - **64.235.151.139:5901**
3. Enter the password to authenticate to your VM - **HyhTTxpi**

9. To connect to the VM and take control of it, launch a VNC client and enter the **IP Address** and **Password** provided in the VNC column. To use Cloud LiveBoot for retrieving files and folders from the VM, Barracuda recommends using a VNC client with file transfer capability such as TightVNC, UltraVNC, or RealVNC (Professional or Enterprise subscription required).
10. By default, the VM is provided a local or internal IP Address/network interface. When the **Interface Type** is set to **Internal**, the VM is not connected to the Internet. To enable Internet access, atop the VM, then click the **Edit** link in the **Interface Type** column. In the **Interface Type** dialog box, click **External**, and click **Done**. Click **Restart** to reboot the VM. Use the network settings provided in the **Interface Type** column to configure the IP address, subnet mask, and default gateway inside the guest OS. Repeat this process to switch back to the **Internal** Interface Type:

### Interface Type ✕

Internal  External

**MAC Address:** 00:0c:29:c4:e6:6d  
**Public IP Address:** 173.225.179.211  
**Subnet Mask:** 255.255.255.240  
**Default Gateway:** 173.225.179.209

**Done**

11. When done with the VM, click **Stop**, then click **Destroy**. This powers off the VM and permanently deletes the instance from the Barracuda Cloud. If you wish to keep your changes and download a copy, click **Download**.

## Figures

1. AddVMCloudLiveBoot.png
2. SelectVMCloudLiveBoot.png
3. VNCPreview.png
4. InterfaceType.png

© Barracuda Networks Inc., 2021 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.