

How to Add a New CloudGen Firewall to the Control Center

https://campus.barracuda.com/doc/79463145/

To add a CloudGen Firewall deployed in the public cloud (Azure, AWS, or Google Cloud Platform) to the Control Center, see How to Import an Existing CloudGen Firewall into a Control Center.


Before you deploy a new firewall, you can create and configure all necessary settings on the Control Center. Then, deploy the PAR file to the firewall.

Step 1. Create a New CloudGen Firewall Configuration in the Control Center

Create a box in the Control Center. If you want to add a firewall with similar settings as a box that already exists on your Control Center, you can also clone the configuration.

To create a new CloudGen Firewall configuration:

- Expand the Boxes node (CONFIGURATION > Configuration Tree > Multi-Range > your range > your cluster).
- Right-click Boxes and select Create Box Wizard.




The **Wizard** window opens.

- 3. Enter all settings requested by the **Create Box Wizard**.
- 4. Click Finish.
- 5. Click **Activate**.

To clone a CloudGen Firewall box:

- 1. Expand the Boxes node (CONFIGURATION > Configuration Tree > Multi-Range > your range > your cluster).
- 2. Right-click the box you wish to clone and select **Clone Box Wizard**.






The **Wizard** window opens.

You can also right-click **Boxes** and select **Clone Box Wizard**. In this case, you must also select the **Box to clone** in the configuration.

- 3. Enter the name of the new box in the **Naming Replace To** field.
- 4. In the Management IP field, enter the IP address of the new box.



- 5. Adjust all settings according to your requirements.
- 6. Click Finish.
- 7. Click Activate.

Step 2. (optional) Configure the Remote Management Tunnel

If your firewall cannot directly access the Control Center, configure a remote management tunnel. For more information, see <u>How to Configure a Remote Management Tunnel for a CloudGen Firewall</u>.

Step 3. Activate the CloudGen Firewall Configuration



Imported firewalls are disabled per default. Disabled CloudGen Firewalls are represented by a gray status icon.

- 1. Open the **Box Properties** page for the CloudGen Firewall (**CONFIGURATION** > **Configuration Tree** > **Multi-Range** > **your range** > **your cluster** > **your CloudGen Firewall**).
- 2. In the left menu, click **Operational**.
- 3. Set **Disable Box** to **no**.
- 4. Click Send Changes and Activate.

The status of the CloudGen Firewall on the **Status Map** (**CONTROL** > **Status Map**) now changes from gray (offline) to red with dashes (unreachable).

Step 4. Deploy the PAR file to the CloudGen Firewall

Deploy the configuration of the new CloudGen Firewall to the remote CloudGen Firewall.

Step 4.1 Create the PAR file on the Control Center

- 1. Log into the Control Center.
- 2. Expand the node for the firewall you imported in Step 2.
- 3. Right-click the box name and select **Create PAR file for box**.
- 4. Choose the destination folder and click **Save**.

Step 4.2. Import the PAR on the CloudGen Firewall

- 1. Log into your firewall.
- 2. Go to CONFIGURATION > Configuration Tree > Multi-Range > your range > your cluster > your CloudGen Firewall.
- 3. Right-click the **Box** node and select **Restore from PAR file**.
- 4. Click OK.
- 5. Select the PAR file created in Step 4.1. and click **Open**.
- 6. Click Activate.

Step 4.3. Activate the Network Configuration

- 1. Go to **CONTROL > Box**.
- 2. In the left menu, expand the **Network** section.
- 3. Click Activate new network configuration.
- 4. In the dialog window, click **Failsafe**.
- 5. In the left menu, expand **Operating Systems** and click **Firmware Restart**.
- 6. Click YES. The firmware of the CloudGen Firewall restarts.

Barracuda CloudGen Firewall



The status of the CloudGen Firewall is now green, red, or yellow. It can take a couple of minutes for the remote firewall to initiate a management tunnel.

Barracuda CloudGen Firewall



Figures

- 1. cb00.png
- 2. cb1.png
- 3. cb02.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.