

# Example - Client-to-Site IKEv2 IPsec VPN with Username/Password Authentication

https://campus.barracuda.com/doc/96026126/

Use an IPsec IKEv2 client-to-site VPN to let mobile workers connect securely to your Barracuda CloudGen Firewall with a standard compliant IKEv2 VPN client.



# **Supported VPN Clients**

Although any standard-compliant IPsec IKEv2 client should be able to connect via IPsec, Barracuda Networks recommends using the following clients:

- Windows 8.1/Windows 10 native IKEv2 IPsec VPN client
- Windows 10 Mobile 10.0.14393 or newer
- Native Android IPsec VPN Client

# **Before You Begin**

- Set up the VPN certificates for external CA. For more information, see <u>How to Set Up External</u> <u>CA VPN Certificates</u>.
- Configure MS-Chapv2 authentication. For more information, see <u>How to Configure MS-CHAP</u> <u>Authentication</u>. For RADIUS-based authentication, this step is not required.
- Identify the subnet and gateway address to use for the VPN service in your network (e.g., 192.168.6.0/24 and 192.168.6.254).
- Identify the IPv4 and IPv6 addresses the VPN service is listening on. If you are using a dynamic WAN IP, see <u>How to Configure VPN Access via a Dynamic WAN IP Address</u>.

# Step 1. Prepare VPN Certificates



1. Get the corresponding root certificate (or create a new one) that should be used to issue a VPN server certificate.

The root certificate must be considered as trusted on the client device (e.g., by importing it into the Trusted Root Certification Authorities Certificate Store on Windows).

- 2. Create a new VPN server certificate by using the CA from above with the following requirements:
  - Hostname of the VPN server that is entered on the client must be contained in the subjectAltName field of the certificate.
  - Required Key Usage fields:
    - Non-Repudiation, Digital Signature, Key Encipherment
  - Required EKU fields:
    - IP Security IKE Intermediate / IP Security End Identity in xCA (OID 1.3.6.1.5.5.8.2.2)
    - Server Authentication (OID 1.3.6.1.5.5.7.3.1)

You should now have a root certificate in CER or PEM format and a VPN certificate in PKCS12, CRT, or PEM format.

# Step 2. Add Certificates to VPN Settings

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > VPN Settings.
- 2. Click Lock.
- 3. In the left menu, select **Root Certificates**.
- 4. Right-click the table and click **Import CER from File** or **Import PEM from File**, depending on the format of your root certificate.
- 5. Select and upload the root certificate created in Step 1.
- 6. In the left menu, select **Service Certificates**.
- 7. Right-click the table and click the **Import Certificate** menu item matching your VPN server certificate.
- 8. Select and upload the VPN certificate created in Step 1.
- 9. In the left menu, select **Service Keys**.
- 10. Right-click the table and select **New Key**.
- 11. Enter a Key Name.
- 12. Select the **Key Length**.
- 13. Click **OK**.
- 14. Click Send Changes and Activate.

#### **Step 3. Create the VPN Client Network**



All VPN clients will receive an IP address from the VPN client network with a static gateway. You can choose the gateway IP address freely from the subnet.

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > VPN Settings.
- 2. Click Lock
- 3. In the left menu, select **Client Networks**.
- 4. Right-click the table and select **New Client Network**. The **Client Network** window opens.
- 5. In the **Client Network** window, configure the following settings:
  - Advertise Route Select check box to include the VPN network in the OSPF or BGP network.
  - **Name** Enter a descriptive name for the network.
  - **Network Address** Enter the base network address for the VPN clients.
  - **Gateway** Enter the gateway network address.
  - Type Select routed (Static Route). VPN clients are assigned an address via DHCP (fixed or dynamic) in a separate network reserved for the VPN. A static route on the firewall leads to the local network.
- 6. Click **OK**.
- 7. Click Send Changes and Activate.

# Step 4. Configure IKEv2 Phase 1 and 2

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > Client to Site.
- 2. Click Lock.
- 3. Click the **External CA** tab.
- 4. Clear the Hide Advanced Configuration check box.



- 6. In the **IKEv2 Phase 1 (default)** section, double-click on the Phase 1 encryption settings. The **Change IPsec Phase 1** window opens.
- 7. Configure the **IPsec Phase I** encryption settings:
  - Encryption Select AES256.
  - Hash Meth Select SHA.
  - **DH-Group** Select **Group 2**.
- 8. (optional) Set the IPsec Phase 1 Lifetime settings:



- Time Enter 3600
- Minimum Enter 1200
- Maximum Enter 4800
- 9. Click **OK.**

Change IPSec Phase 1 Settings			
For Certificate Authentication			
IDCos Dhase 1	r		
Ensuration		_	
Encryption	AES256	•	
Hash Meth.	SHA	-	
DH-Group	Group 2	-	
Lifetime			
Time		3600	
Minimum		1200	
Maximum		4800	
ОК		Cancel	

- 10. Right-click in the IKEv2 Phase 2 table and select New IKEv2 Phase II. The IPsec IKEv2 Phase II windows opens.
- 11. Enter a Name.
- 12. Configure the IPsec phase 2 encryption settings:
  - Encryption Select AES256.
  - Hash Meth Select SHA.
  - **DH-Group** Select **Group 2**.
- 13. (optional) Set the IPsec Phase 2 Lifetime settings:
  - Time Enter 3600
  - Minimum Enter 1200
  - Maximum Enter 4800
- 14. Click **OK**.



IPSec IKEv2 P	hase II
Name	IKEv2PhaseII Disabled
Encryption	AES256 💌
Hash Meth.	SHA 💌
DH-Group	Group 2
Lifetime	
Time	3600
Minimum	1200
Maximum	4800

15. Click Send Changes and Activate.

# Step 5. Configure VPN Common Settings

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > Client to Site.
- 2. Click **Lock**.
- 3. Click the **External CA** tab.
- 4. Click the **Common** sub-tab.
- 5. Right-click the table and select **New Common**. The **Common Settings** window opens.
- 6. Enter a Name.
- 7. (optional) Enter a **Statistic Name**. For more information, see <u>Statistics</u>.
- 8. From the **Assigned Network** drop-down list, select the VPN network created in Step 3.
- 9. (optional) Enter the **DNS** server IP address.
- 10. (optional) Enter the **WINS** server IP address.
- 11. Enter the **Network Routes** that should be sent through the VPN tunnel and click **Add**. To send all traffic through the VPN tunnel, enter 0.0.0/0.
- 12. (optional) To limit the source from which VPN connections are accepted, add the IP addresses or subnets to the **Access Control List (ACL)**.

# Barracuda CloudGen Firewall



Isert new Common	Settings
Common	
Name	C2S-Common
Statistic Name	
Assigned Network	VPNClientNetwo 192.168.111.0
DNS	8.8.8.8
WINS	
Add Delete	10.0.0/24
Access Control List (A(	CL)
	Addr/Mask
Add Delete	

- 13. Click **OK**.
- 14. Click Send Changes and Activate.

#### Step 6. Configure a VPN Group Policy

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > Client to Site.
- 2. Click Lock.
- 3. Click the **External CA** tab.
- 4. Click the **Policy** sub-tab.
- 5. Right-click in the table and select **New Policy**. The **Group VPN Policy** window opens.
- 6. Enter a Name.
- 7. In the **Common** tab, select the VPN common settings you created in Step 5 from the **Link to** drop-down list.

# Barracuda CloudGen Firewall



up VPN Policy		(
sert new Group \	VPN Policy	
lame C2SIKEv2	Disabled	
common () Barracu	uda () IPSec () IPsec IKEv2 ()	
	S Common - Edit Ne	214/
LUDIC TO		
LINK to C2		
Name	: C25-Common	
Name Statistic Name	: C25-Common	
Name Statistic Name Assigned Network	: C2S-Common : : VPNClientNetwork (192.168.111.1+dyn)	
Name Statistic Name Assigned Network DNS WINS	: C25-Common : : VPNClientNetwork (192.168.111.1+dyn) : 8.8.8.8 :	
Name Statistic Name Assigned Network DNS WINS Routes	: C25-Common : : VPNClientNetwork (192.168.111.1+dyn) : 8.8.8.8 : : 10.0.0.0/24	

- 8. Click the **IPsecIKEv2** tab.
- 9. Select the IPsec IKEv2 Phase 2 settings from the **Link to** drop-down list.

ommon () Barr	acuda () IPSec () IPsec	: IKEv2 ()
Link to	IKEv2PhaseII 🔻	Edit New
Name	: IKEv2PhaseII	
Disabled	: No	
Encryption	: AES256	
Hash Meth.	: SHA	
DH-Group	: Group 2	
Lifetime		
Time	: 3600	
Minimum	: 1200	
Maximum	: 4800	

- 10. Click **OK**.
- 11. Click Send Changes and Activate.

# **Step 7. Configure VPN Rules**

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > Client to Site.
- 2. Click Lock.
- 3. Click the External CA tab.
- 4. Click the **Rules** sub-tab.
- 5. Right-click in the table and select **New Rule**. The **Group Policy Condition** window opens.
- 6. From the **Assigned VPN Group** list, select the group VPN policy created in Step 6.
- 7. (external authentication only) Enter a **Group Pattern** to define the groups that will be assigned



the policy. E.g.: CN=vpnusers\*

- 8. In the **Peer Condition** section, verify that the **IPsec Client** check box is selected.
- 9. (optional) In the **X509 Certificate Conditions** section, enter matching conditions for the X.509 client certificates.

Assigned VPN Gro	ID C2SIKEv2	•
External Group Condit	on (from external authentication)	
Group Pattern	CN=vpnusers*	Lookup
example	memberOf: CN=group 1,CN=Users,D Pattern 1: "CN=Users > * substitute Pattern 2: CN=group? > ? substitute	C=smard,DC=test is for any zero or more character is for any one character
X509 Certiticate Cond	tions	
Subject		Edit/Show
Certificate Policy		(OID: 2.5.29.32)
Generic v3 OID		•
	Content	
Peer Condition		
Barracuda Client	☑ Transparent Agent (SS	SL-VPN)

- 10. Click **OK**.
- 11. Click Send Changes and Activate.

# Step 8. Configure Group VPN Settings

- 1. Go to CONFIGURATION > Configuration Tree > Box > Assigned Services > VPN-Service > Client to Site.
- 2. Click Lock.

4.

3. Click the **External CA** tab.

Click th	Click the <b>Click here for options</b> link.					
Barracuda V	/PN CA External CA	Message	es   Pictures   😵 Reg	istry 🛛 😅 VPN FW	😅 Offline FW	
Group Polic	Group Policy Rules Policy Common Barracuda IPSec Hide Advanced Configuration					
Click here for options						
Disabled	Name	Secure	Network	Routes	External Group	
No	C2SIKEv2		192.168.111.1+dyn	10.0.0/24	*	

- 5. From the Authentication Scheme drop-down list, select Default Authentication Scheme.
- 6. From the Default Authentication Scheme drop-down list, select msad or radius.
- 7. From the **Server** drop-down list, select the VPN server certificate uploaded in Step 2.
- 8. From the **Server Protocol Key** drop-down list, select the service certificate created in Step 2.
- 9. From the **Used Root Certificates** drop-down list, select the root certificate uploaded in Step 2.
- 10. Click **OK**.
- 11. Click Send Changes and Activate.



#### **Step 9. Add Access Rules**

Add an access rule to connect your client-to-site VPN to your network.

For more information, see <u>How to Configure an Access Rule for a Client-to-Site VPN</u>.

#### **Monitoring VPN Connections**

On the **VPN > Client-to-Site** page, you can monitor VPN connections. The page lists all available client-to-site VPN tunnels. In the **Tunnel** column, the color of the square indicates the status of the VPN:

- **Blue** The client is currently connected.
- Green The VPN tunnel is available, but currently not in use.
- **Grey** The VPN tunnel is currently disabled. To enable the tunnel, right-click it and select **Enable Tunnel**.

For more information on the **VPN > Client-to-Site** page, see <u>VPN Tab</u>.

#### Troubleshooting

To troubleshoot VPN connections, see the srv\_<SERVER\_NAME>\_<VPN\_SERVICE\_NAME>\_IKEv2.log log file. For more information, see LOGS Tab.

#### **Next Step**

Configure the remote access clients to connect to the client-to-site VPN.

For more information, see <u>Remote Access Clients</u>.



#### Figures

- 1. Client2SiteIPsecVPN.png
- 2. C2S\_IKEv2\_02b.png
- 3. C2S\_IKEv2\_03.png
- 4. C2S IKEv2 04.png
- 5. C2S IKEv2 05.png
- 6. C2S\_IKEv2\_06.png
- 7. C2S IKEv2 07.png
- 8. C2S IKEv2 08.png
- 9. C2S IKEv2\_09.png
- 10. C2S IKEv2 11.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.