

Resources Page


https://campus.barracuda.com/doc/96026488/

The **Resources** page provides information on active processes on the Barracuda CloudGen Firewall, such as the machine uptime, number of logged-in-users, load average, and memory usage. To access the **Resources** page, open the **CONTROL** tab and click the **Resources** icon in the ribbon bar.



Processes Section

The processes section gives an overview of all active processes running on the CloudGen Firewall.



The table header includes additional control elements that allow you to control the display of process information.

- **Show Details...** Get detailed information on an active process.
- **Single PID** If checked, child processes in table are also displayed.
- **HH:MM:ss up X days** Uptime of the firewall since last restart.

Resources Page 1/7



Mainboard Info... - Get detailed information on the mainboard of the firewall.

The **Processes** table shows information on active processes. You can also view detailed information on a selected entry and track each task to a single process.

Information for each process or process group is organized in the following columns:

- **Name** The name of the process. Small graphical bars to the left of the name indicate the CPU load in percent, ranging from 0%, 10%, 25%, 50%, 70% to 90%.
- **Proc** The number of processes with the same name.
- %CPU The percentage of CPU load that is used.
- **Num FD** The number of file descriptors used by processes with this name.
- **Memory** The amount of memory (in kB) used exclusively by processes with this name.
- **Shared** Shared memory in kB used by processes with this name.
- Listen The number of listening TCP sockets owned by processes with this name.
- **Establ.** The number of established sockets owned by processes with this name.
- **UDP** The number of UDP sockets owned by processes with this name.
- **Syn Sent** The number of unanswered SYN packets sent by processes with this name / t he number of unanswered SYN packets for which the timeout has not yet expired.
- **Close** The number of sockets owned by processes with this name.
- Last ACK The number of sockets in state LAST ACK owned by processes with this name.

Order of Processes

By default, processes are displayed in ascending order by their name. This is indicated by the blue highlighted category label. The small triangle indicates the sort order of the displayed table entries, which can be either ascending or descending.

To change the sort order, click on the corresponding label of a table category.

Reordering Columns in the Process Table

To reorder the columns in the process table, drag and drop the column header to your desired position.

Selecting Categories for Display in the Processes Table


You can customize the categories of the columns displayed in the process table.

Resources Page 2/7



To specify the information category of your choice:


- 1. Right-click inside of the display area of the processes table.
- 2. In the pop-up menu, click on **Select Columns...**.
- 3. From the **Available Columns** table, select the category that you want to be displayed in the process list.
- 4. Click on the > button to move the information field from the column Available Columns to the Current Columns. Entries in the table Current Columns will be displayed in the list order. Click on < to remove the category from the values to be displayed.</p>
- 5. To the apply the changes, click **Close** .



Viewing Process Details

To view details on a running process:

- 1. Select a process in the process list table.
- 2. Click **Show details...** at the top left of the table.




The **Info Dialog** window opens with the following information on the selected process:

Resources Page 3/7




- The process IDs of all processes with the same name.
- Detailed list of all open files.
- The IP addresses and ports of listening TCP sockets.
- The local IP:port and remote IP:port combinations of all established sockets.
- The IP addresses and ports of UDP sockets.



Displaying Subprocesses

Processes can create a hierarchical order of child processes. The list is updated every two seconds and includes all child processes.

Check the box **Single PID** to show child processes in the list.




Displaying Information on the Mainboard

Click **Mainboard Info...** to display information on the mainboard.


Resources Page 4/7

Barracuda CloudGen Firewall






The **Mainboard Info** window opens with a detailed breakdown of technical information on your underlying system.



System Section

The system section displays the usage of RAM and disk space in real time. For hardware systems, you can also view the temperature and fan speed. (CD-ROMs and floppy disks are not displayed.)



Resources Page 5 / 7

Barracuda CloudGen Firewall



The following information is provided:

- CPU Displays the current CPU load of the CloudGen Firewall.
- **Disk Space** Displays real-time usage of all currently mounted file systems. Each file system is identified by its mount point. In a default installation of the CloudGen Firewall, the following file systems at a minimum should be present:
 - ∘ / Root directory.
 - /boot Directory for boot images (usually located at the beginning of a disk).
 - /phion0 Directory for logs and statistical data.
- RAM Displays the real-time usage of RAM.
- **Temperature** Displays the temperature of the mainboard and CPU.
- Fan Speed Displays the speed of the chassis fan.

Resources Page 6 / 7

Barracuda CloudGen Firewall



Figures

- 1. resources_page_00.png
- 2. processes section 00.png
- 3. select_information_category_00.png
- 4. show details 00.png
- 5. res page 02.png
- 6. include_child_processes_00.png
- 7. mainboard info 00.png
- 8. mainboard_info_01.png
- 9. system_section_00.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Resources Page 7/7