

Revision Control System (RCS)

<https://campus.barracuda.com/doc/41116170/>

The Revision Control System (RCS) stores versioning information on all configuration changes to your system (except the DNS service). You can view and, if necessary, revert to older configuration versions as needed.

The DNS service is not supported by RCS.

In this article:

Step 1. Enable the Revision Control System

After configuring RCS on a Barracuda NG Control Center, you must *restart* the **CC Configuration service** and your Barracuda NG Control Center session.

1. Open the **CC Parameters** page (**Config > Multi-Range > Global Settings**).
2. In the left menu, click **RCS Setup**.
3. From the **Version Control System** list, select **Enable**.
4. Define the following RCS settings:
 - **Log Change Differences** - Enables or disables the RCS log (file name: *servicename_changes*) of all configuration changes.
 - **Log Creation Differences** - Specifies how configuration changes are logged. You can select one of the following settings:
 - **Difference-to-Default** - Only differences to the default settings are listed.
 - **Full-Info** - Every setting is listed.
 - **None** - Only changes are listed.
 - **Log Removal Differences** - Specifies how to log file removals. You can select one of the following settings:
 - **Difference-to-Default** - Only differences to the default settings are listed.
 - **Full-Info** - Every action is listed.
 - **None** - The removal of files is not listed.
 - **Report Processing Script** - You can enter a script to automate the transmission of change reports to other destinations. The shell script can invoke Secure Copy (scp) or email delivery. Example scripts are listed at the bottom of this page.
 - **Force RCS Change Message** - To enter a comment for every RCS check-in, select **yes**.
5. Click **Send Changes** and **Activate**.

Step 2. Restart the CC Configuration Service

After enabling RCS, the **CC Configuration service** must be restarted as well as your Barracuda NG Control Center session.

1. Log into the box layer of your NG Control Center.
2. Open the **Server** page (**CONTROL > Server**).
3. In the **Service Status** table, select the **CONF (CC-Configuration-Service)** service and click **Restart Service**.

Depending on the size of the configuration tree, this may take several minutes because each configuration tree entry is given its own version number. To get status information, see the CONF\changes log.

4. Log out.

Next Steps

After configuring and activating RCS, you can view change reports for each Config Tree node. For more information see [How to View and Revert RCS Versions](#). To display the RCS function in the configuration, you must log out and back into NG Admin.

Report Processing Script Examples

The following table displays examples of scripts that you can enter in the **Report Processing Script** table for transmitting your change reports via scp or mailclt. In your script, use the \$REPORT variable. The name of the report file is stored in \$REPORT.

Method	Example Script
scp	scp "\$REPORT" user@yourserver.com
mailclt With the -m option, you must specify the IP address of a reachable SMTP server because DNS resolution is not supported by RCS. Do not specify the MX record.	/opt/phion/bin/mailclt -f sender@sender.com -r recipient@recipient.com -s "change" -m 192.168.0.1 -a "\$REPORT"

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.