

## How to Move, Copy and Delete Barracuda NG Firewalls

<https://campus.barracuda.com/doc/43846868/>

You can freely move, copy or delete managed Barracuda NG Firewalls on the NG Control Center. When moving or copying systems which link to a repository make sure the repository is also available from the destination node, or the links to the repository will be broken and replaced by a copy of the repository configuration instead.

### In this article:

#### Move a Barracuda NG Firewall without Links to a Repository

1. In the **Configuration Tree**, navigate to the Barracuda NG Firewall that you want to move.
2. Right-click the Barracuda NG Firewall and select **Lock**.
3. Right click the Barracuda NG Firewall and select **Move Box**.
4. Select the new location and enter a new name for the Barracuda NG Firewall. The name cannot contain more than 25 characters.
5. Click **OK**. The Barracuda NG Firewall is then moved.

#### Moving a Barracuda NG Firewall with Links to a Repository

Moving a Barracuda NG Firewall configuration with links to a [How to Set Up Repositories](#) the links may break when moving the system depending on whether it is a global, range or cluster repository. The settings on the previously linked configuration pages will be saved, but the pages are no longer linked to the repository.

Repository	Move or Copy to a Different Range	Move or Copy to a Different Cluster
Global	Link remains	Link remains
Range	Link is broken	Link remains
Cluster	Link is broken	Link is broken

#### Remove a Barracuda NG Firewall

A Barracuda NG Firewall that has been removed from the Barracuda NG Control Center does not automatically become a standalone system. If you want to use the removed Barracuda NG

Firewall as a standalone system, you must reconfigure it.

1. In the **Configuration Tree**, navigate to the Barracuda NG Firewall that you want to remove.
2. Right-click the Barracuda NG Firewall and select **Lock**.
3. Right-click the Barracuda NG Firewall and select **Remove Box**.
4. Click **OK**.

After the Barracuda NG Firewall has been removed, the box entry should disappear from the CC status map with the next configuration update. If the entry stays on the system:

1. At the command line, enter the following commands:  

```
$ find /opt/phion/rangetree/configroot/ -name box.dbconf | xargs rm  
$ conftool r - rebuild_db  
$ conftool r - rebuild_cache
```
2. Restart the CC Rangeconf service.

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.