

## How to Move, Copy, and Delete F-Series Firewalls in the Control Center

<https://campus.barracuda.com/doc/48202916/>

You can freely move, copy, or delete managed Barracuda F-Series Firewalls on the NextGen Control Center. When moving or copying systems which link to a repository make sure the repository is also available from the destination node, or the links to the repository will be broken and replaced by a copy of the repository configuration instead.

### Move a NextGen Firewall F without links to a repository

1. In the **Configuration Tree**, navigate to the Barracuda NextGen Firewall F-Series that you want to move.
2. Right-click the Barracuda NextGen Firewall F-Series and select **Lock**.
3. Right click the Barracuda NextGen Firewall F-Series and select **Move Box**.
4. Select the new location and enter a new name for the Barracuda NextGen Firewall F-Series. The name cannot contain more than 25 characters.
5. Click **OK**. The Barracuda NextGen Firewall F-Series is then moved.

### Moving a NextGen Firewall F with links to a repository

Moving a Barracuda NextGen Firewall F-Series configuration with links to a [repository](#) the links may break when moving the system depending on whether it is a global, range or cluster repository. The settings on the previously linked configuration pages will be saved, but the pages are no longer linked to the repository.

Repository	Move or Copy to a Different Range	Move or Copy to a Different Cluster
Global	Link remains	Link remains
Range	Link is broken	Link remains
Cluster	Link is broken	Link is broken

### Remove a NextGen Firewall F

A Barracuda NextGen Firewall F-Series that has been removed from the Barracuda NextGen Control Center does not automatically become a standalone system. If you want to use the removed Barracuda NextGen Firewall F-Series as a standalone system, you must reconfigure it.

1. In the **Configuration Tree**, navigate to the Barracuda NextGen Firewall F-Series that you want to remove.
2. Right-click the Barracuda NextGen Firewall F-Series and select **Lock**.
3. Right-click the Barracuda NextGen Firewall F-Series and select **Remove Box**.
4. Click **OK**.

After the Barracuda NextGen Firewall F-Series has been removed, the box entry should disappear from the CC status map with the next configuration update. If the entry stays on the system:

1. At the command line, enter the following commands:  

```
$ find /opt/phion/rangetree/configroot/ -name box.dbconf | xargs rm  
$ conftool r - rebuild_db  
$ conftool r - rebuild_cache
```
2. Restart the CC Rangeconf service.

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.