

How to Configure Access Notifications

<https://campus.barracuda.com/doc/53248748/>

Access notification settings assign notification types to each Barracuda NextGen Firewall F-Series service or otherwise relevant system service (for example, `sshd` or console login). The service uses the login ID attempting access to verify its legitimacy on the system. Next, it determines the associated notification scheme for the login ID with the service default constituting a fallback option. Finally, it determines the service-specific notification type from the applicable notification scheme and generates an appropriate event. There are two simple scenarios:

- Login attempts with an unknown login ID trigger Event-ID *4100 User Unknown*.
- The authentication process fails for some other reason, creating Event-ID *4110 Authentication Failure Notice*.
Authentication failure on the second login attempt generates Event-ID *4111 Authentication Failure*.
- If the maximum number of authentication attempts (usually 3) is exceeded, a *Event-ID 4112 Authentication Failure Alert* notification is generated. This is only possible if an internal system error has occurred.

Configure Access Notifications

You can configure the following access notification types:

- **Silent** - (Automatically assigned to invisible users *ha* and *master*) Suppresses notifications for successful access attempts. Unsuccessful attempts are treated according to the **Service Default** scheme.
 - **Notice** - Generates a *Notice* event.
 - **Warning** - Generates a *Warning* event.
 - **Alert** - Generates an *Alert* event.
1. Go to **CONFIGURATION > Full Configuration > Box > Advanced Configuration > Access Notification**.
 2. In the left menu, select **Basic Setup**.
 3. Click **Lock**.
 4. In the **Console Access** section, select the notification types for the following access settings:
 - **Sys-CMD: su** - The notification type for the `su` (Substitute User) command-line tool. The notification settings used are not those of the system user invoking `su` but the system user whose identity is adopted.
 - **Sys-CMD: login** - The notification type for a successful login. Note that login here denotes direct system access via the console.
 - **SSH: login** - The notification type for a successful system access via the SSH protocol.
 - **SSH: rexec** - The notification type for an access via the SSH protocol for remote command execution. Note that remote copy (*scp*) and secure FTP (*sftp*) would also fall

into this category.

With the exception of the SSH: rexec setting, the services do not have adjustable settings for failed access attempts. Access failures at the operating system level are always recorded.

5. Click **Send Changes** and **Activate**.

Configure the Message Board

Configure the messages to be displayed at login time via SSH, the Barracuda NextGen Admin GUI, and on the console.

1. Go to **CONFIGURATION > Full Configuration > Box > Advanced Configuration > Message Board**.
2. In the left menu, select **Basic Setup**.
3. Click **Lock**.
4. In the **Message Display Policy** section, select when to display a message.
5. In the **Displayed Message** section, adjust the message as required. Use only:
 - Alphabetic characters
 - Numerics
 - # ! _ , .Empty breaks, repeated spaces, and a single period (.) in an empty line will be ignored.
6. Click **Send Changes** and **Activate**.

It is recommended that you check the display of the message at the login after editing.

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.