


## How to Renew a Pool License

<https://campus.barracuda.com/doc/54264867/>




When your pool licenses are renewed, they are automatically downloaded to the Control Center and thereby replace the old pool license. All managed firewalls using the pool license enter grace mode until the admin reassigns the license to all instances of the pool license. Note that the licenses are not assigned and updated automatically because a maintenance window is required to update the licenses. In addition, reassigning the licenses manually also safeguards against invalid licenses that do not match the Control Center or use invalid start / expiration dates. The licenses on the managed firewall must be reassigned before the two-week grace period expires.

### Before you begin

- Renew your pool licenses.
- The Control Center automatically downloads the new license.
- All managed firewalls enter grace mode. Event 500 **Invalid License** is triggered for each of them.
- Go to **CONFIGURATION > Configuration Tree > Multi-Range > Global Settings > CC Identity** and write down the **CC Identifier**.



CC Identification


Organization	Campus Barracuda Networks	
CC Identifier	ngcc-	
CC Product License	lic=	

Show... Import Clear


### Step 1. Verify the pool license

Before updating the licenses on the Control Center, verify that the pool license was created for your Control Center and that the start and expiration dates of the license are correct.

1. Log in to the Control Center.
2. Go to **CONFIGURATION > Configuration Tree > Multi-Range > Global Settings > Pool Licenses**.
3. Double-click on the renewed pool licenses. The **Certificate View** window opens.




4. In the **Barracuda** section, scroll down and verify that the **master** matches the **CC Identifier** of the Control Center.



5. Click **Detail View**.

6. Verify that the start and expiration date match the license you purchased and that the start date is not in the future.



## Step 2. Reassign the pool license to the managed firewalls

Trigger automatic reassignment of the pool license for the managed firewalls to switch to the

renewed pool license.

1. Go to **CONTROL > Barracuda Activation**.
2. In the **Pool Licenses** section, right-click on the renewed pool license and click **Reassign Licenses to Instances**.

Pool Licenses									
Activation State	Model	License ID	Instances	Used	Serial	Start Date	End Date	Activation Token	Info
Activated	VF25	bn-vi25-pool-	10	0.00% (0 of 10)	678762	10.05.2016	19.05.2021		Licenses up to date
Activated	VF2000	bn-vi2000-pool-	10	0.00% (0 of 10)	678763	27.08.2015	05.09.2020		Licenses up to date
Activated	VF2000	bn-vi2000-pool-	20	0.00% (0 of 20)	784203	10.05.2016	19.05.2019		Licenses up to date

- Import Pool License
- Remove Pool BAR-NG-
- Use Unattended Activation
- Update Licenses on CC
- Move Instances to another Pool ...
- Reassign Licenses to Instances**
- Refresh
- Tools

3. Click **Yes**.
4. Click **OK**.

Go to **CONTROL > Floating Licenses** to verify that the **License State** column is green for all managed firewalls that have received a license in the renewed pool license.

## Figures

1. renew\_poollic\_00.png
2. renew\_poollic\_01.png
3. renew\_poollic\_02.png
4. renew\_poollic\_03.png
5. renew\_poollic\_04.png

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.