

## How to Configure Failover and Load Balancing in Custom Connection Objects


<https://campus.barracuda.com/doc/79462989/>

For custom connection options you can configure failover and load balancing policies. You can configure up to 7 alternatives to the default translated source IP policy.

### Step 1. Create a Custom Connection Object

Create a custom connection object using one of the following **Translated Source IP** policies:

- **Original Source IP**
- **Dynamic NAT**
- **Network Interface**
- **Explicit IP**



The screenshot shows the configuration interface for a custom connection object. The 'General' section includes fields for Name (LoadBalancingConnObject), Description, Color Label, and Timeout (30). The 'NAT Settings' section, highlighted with an orange border, includes a dropdown for Translated Source IP (Network Interface), Interface Name (dhcp), and Weight (10).

For more information, see [How to Create a Custom Connection Object](#).

### 2. Configure Failover and Load Balancing Settings

In the **Failover and Load Balancing** section of the custom connection object you created in step 1 you can configure the policy and the alternative translated source IPs.

#### Failover

1. From the **Policy** list select **Failover**.
2. Click **+** to add alternative connections to the **Alternatives** list.
3. For each entry click on the edit symbol in the **Type** column and select how the translated source IP is determined:
  - **Explicit IP** – Enter the new source IP address in the **Value** column.
  - **Network Interface** – Enter the network interface in the **Value** column.
  - **Original Source IP**
  - **Dynamic NAT**

Failover and Load Balancing

Policy

**Alternatives** + × ↕

Type	Value
Explicit IP	194.93.0.10
Network Interface	ppp5
Original Source IP	
Dynamic NAT	

4. Click **OK**.
5. Click **Send Changes** and **Activate**.

## Weighted Round Robin

1. From the **Policy** list select **Weighted Round Robin**.
2. Click **+** to add alternative connections to the **Alternatives** list.
  - **Explicit IP** – Enter the new source IP address in the **Value** column.
  - **Network Interface** – Enter the network interface in the **Value** column.
  - **Original Source IP**
  - **Dynamic NAT**
3. (optional) In the **NAT Settings** enter the **Weight**.
4. (optional) In the **Alternatives** list enter the **Weight** for each alternative connection.

NAT Settings

Translated Source IP

Interface Name  Weight

Failover and Load Balancing

Policy

**Alternatives** + × ↕

Type	Value	Weight
Explicit IP	194.93.0.10	5
Network Interface	ppp5	5
Original Source IP		2
Dynamic NAT		1

5. Click **OK**.
6. Click **Send Changes** and **Activate**.

## Weighted Random

1. From the **Policy** list select **Weighted Random**.
2. Click **+** to add alternative connections to the **Alternatives** list.
  - **Explicit IP** – Enter the new source IP address in the **Value** column.
  - **Network Interface** – Enter the network interface in the **Value** column.
  - **Original Source IP**
  - **Dynamic NAT**
3. (optional) In the **NAT Settings** enter the **Weight**.
4. (optional) In the **Alternatives** list enter the **Weight** for each alternative connection.

NAT Settings

Translated Source IP

Interface Name  Weight

Failover and Load Balancing

Policy

Alternatives		
Type	Value	Weight
Explicit IP	194.93.0.10	5
Network Interface	ppp5	5
Original Source IP		2
Dynamic NAT		1

5. Click **OK**.
6. Click **Send Changes** and **Activate**.

## Source IP Hash

1. From the **Policy** list select **Source IP Hash**.
2. Click **+** to add alternative connections to the **Alternatives** list.
  - **Explicit IP** – Enter the new source IP address in the **Value** column.
  - **Network Interface** – Enter the network interface in the **Value** column.
  - **Original Source IP**
  - **Dynamic NAT**
3. (optional) In the **NAT Settings** enter the **Weight**.
4. (optional) In the **Alternatives** list enter the **Weight** for each alternative connection.

**NAT Settings**

Translated Source IP

Interface Name  Weight

**Failover and Load Balancing**

Policy

**Alternatives**

Type	Value	Weight
Explicit IP	194.93.0.10	5
Network Interface	ppp5	5
Original Source IP		2
Dynamic NAT		1

5. Click **OK**.
6. Click **Send Changes** and **Activate**.

## Provider Optimization

Provider Optimization selects the optimal TCP connection by determining the provider with the fastest response time to TCP probing packets sent by the firewall. The option requires to specify at least to connections to rival, e.g. an interface, a dynamic IP, an explicit IP.

This option needs to activate Feature Level 8.0.

1. From the **Policy** list select **Provider Optimization**.
2. Click **+** to add connections for probing to the **Alternatives** list.
  - o **Explicit IP** – Enter the new source IP address in the **Value** column.
  - o **Network Interface** – Enter the network interface in the **Value** column.
  - o **Original Source IP**
  - o **Dynamic NAT**
3. (optional) In the **NAT Settings** enter the **Weight**.
4. (optional) In the **Alternatives** list enter the **Weight** for each alternative connection.

**NAT Settings**

Translated Source IP

Weight

**Failover and Load Balancing**

Policy

**Alternatives**

Type	Value	Weight
Explicit IP	194.93.0.10	5
Network Interface	ppp5	5
Original Source IP		2
Dynamic NAT		1

## Next Steps

---

Create a Pass, Dst NAT or Broad-Multicast access rule and select the connection object as the **Connection Method**.

For more information, see [Access Rules](#).

## Figures

1. conn\_obj\_lb\_00.png
2. conn\_obj\_lb\_01.png
3. conn\_obj\_lb\_02.png
4. conn\_obj\_lb\_02.png
5. conn\_obj\_lb\_04.png
6. conn\_object\_provider\_optimization\_01.png

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.