# CudaLaunch for Windows and macOS

https://campus.barracuda.com/doc/73695292/

CudaLaunch offers remote access to services and features in your organization made available to remote users through the SSL VPN service. CudaLaunch requires an Advanced Remote Access subscription. To evaluate CudaLaunch without having to set up a firewall for it, log in with the demo button.

## Firewall Firmware Requirements

To use all available CudaLaunch features, the CloudGen Firewall must run the latest matching firmware version. CudaLaunch is also supported for older firmware versions, starting with 7.0, but not all CudaLaunch features may be available.

## Before You Begin

- (optional) To use the VPN group policies in the **VPN Connection** tab, install the NAC. For more information, see Barracuda Network Access and VPN Client.
- Configure the services and features you want to use in CudaLaunch. For more information, see CloudGen Firewall Configuration for CudaLaunch .

## Download and Install CudaLaunch

Download and install CudaLaunch on your device. The Windows version is available from the Microsoft Windows 10 App Store. The macOS version is available in the macOS App Store.

## Interface

CudaLaunch arranges all available web resources into the following sections, accessible via the interface service bar:

- **Favorites** – Contains the shortcuts to resources for quick access.
- **Apps** – Contains all configured web and Outlook Web Access resources.
- **VPN Connections** – Contains all client-to-site VPN group policies made available by the admin.
- **Tunnels** – Contains the generic SSL tunnels that are either stored on the device or made


available by the admin.

- **Folders** – Contains all configured network file share resources that the user is allowed to access.
- **Rules** – If present, contains all configured dynamic firewall rules that the user is allowed to enable or disable.

## Logging In

To log in, you must have the following information:


- **Hostname or IP address** – The IP address or FQDN resolving to the public IP address the SSL VPN service is listening on.
- **Username**
- **Password**




## Changing Language Settings


You can change the display language for CudaLaunch on the **Settings** page. To do so, click the options icon on the top left and select **Settings > General**.






## Launching Resources

The **Apps** tab contains all the web resources. To launch a resource from the **Apps** screen, click the icon associated with it. Web app resources are launched using the default browser of the operating system.





The web resource launches in a new tab in your network browser, and you are redirected to the application page.

## VPN Apps


VPN Apps establish a secure client-to-site VPN connection to access the remote service behind the firewall. This feature is available on Windows, iOS, and Android. Windows clients are also required to install the Barracuda Network Access or VPN Client.

To launch the VPN connection from the **Apps** screen, click the icon associated with it. The connection is launched using the default browser of the operating system and the user can access internal resources.



As soon as the VPN connection is established, the connection indicator of the icon changes to green.

Click the **VPN Connections** tab to verify the status of the connection.






As soon as the VPN connection is established, the **VPN Connections** page displays the connection status, indicating that the device is connected.

To relaunch the VPN connection, click **Relaunch**. To disconnect, click **Disconnect**. On a Windows system, you can also open the VPN Client menu from the toolbar and select **Disconnect**. As soon as the VPN connection is terminated, the connection indicator of the icon changes to gray.

## Native Apps


When launching native apps such as RDP, CudaLaunch automatically establishes a tunnel in the background and launches the app in a new browser tab.







## VPN Connections

The **VPN Connections** tab contains the VPN group policies configured by the admin for CudaLaunch. The Barracuda Network Access or VPN Client must be installed on the client to be able to start the VPN connection in CudaLaunch. To connect to the client-to-site VPN, click the VPN Group policy.






## Tunnels

Generic tunnels are used to tunnel TCP connections for client/server applications.

Click the **Tunnels** tab. Click one of the generic tunnel profiles that are made available by the admin.





The client connects to a port on the 127.0.0.1 interface. Use the local IP address and port number in the locally installed app.




## Network Places


Network Places provide remote access to corporate file shares made available by the admin. The **Folders** tab allows you to browse network shares and to rename, delete, retrieve, and upload files.

Click the **Folders** tab. Click the 'forward' arrow icons to navigate through the folders and files.




To launch a resource from the **Folders** screen, click the icon associated with it. When prompted for


attributes, enter username and password, and click **Continue**.





Network Places are launched using the default browser of the operating system.

## Adding Favorites

On the **Favorites** page, you can store web resource shortcuts for easier access. Click the **Favorites** tab. To add a web resource to the favorites, click the **+** icon.





Select the item you want to add from the list, and click the check mark icon. The resource you have added is now visible under the **Favorites** tab.





To remove a resource from the favorites list, click the **Favorites** tab and then click the trash can

symbol.





Select the shortcut, and then click the check mark icon .




## Dynamic Firewall Rules


Dynamic firewall rules allow administrative users with the proper permissions to enable access rules for a specific time period. When the time limit is reached, firewall sessions matching these rules are terminated.

Click the **Rules** tab. The dynamic rules page displays all available rules that have been configured in the CloudGen Firewall SSL-VPN Dynamic Firewall Rules configuration.




On the dynamic rules pages, you can:

- Enable dynamic firewall rules by selecting **Enable**.
- Enable dynamic firewall rules on a time schedule basis by selecting **Enable with Time**. When using this option, a time scheduler lets you select the time span for the rule. Select the time (Days, Hours, and Minutes) and click **Done**.





- Disable dynamic firewall rules by selecting **Disable**.

Click the check mark icon to save your changes.

## Setting User Attributes

User attributes are user-specific placeholder values used for web forwards. User attributes can be filled/changed in the options menu. When a web forward is launched for the first time, the user is requested to fill in the user attributes. To fill in or change a user attribute, click **Settings** in the **Options** menu, and click **Personal Information** to see a list of the user attributes for your user.


For more information, see How to Use and Create Attributes.



## Information and Logs

You can view general information about CudaLaunch on the **Info** page. To do so, click the **Options** icon on the top left and select **Info**.

To view logs, version number, and connection details, select **About**. On the **Log** window, you can copy the log files to the clipboard and view the license agreement.




From the **Options** menu, you can also refresh the CudaLaunch configuration. To do so, select **Refresh**.

## Logging Off

To log out of CudaLaunch, expand the **Options** menu on the top left, and then select **Log Out**.

## Figures


1. cudalaunch_dt_01.png
2. cudalaunch_dt_02.png
3. cudalaunch_dt_03.png
4. cudalaunch_dt_04.png
5. vpnapp_05.png
6. vpnapp_06.png
7. cudalaunch_dt_05.png
8. cudalaunch_dt_06.png
9. CudaLauch_VPNConn01.png
10. CudaLauch_VPNConn02.png
11. cudalaunch_dt_07.png
12. cudalaunch_dt_08.png
13. cudalaunch_dt_08b.png
14. cudalaunch_dt_08a.png
15. cudalaunch_dt_09.png
16. cudalaunch_dt_10_no_NetworkPlaces.png
17. cudalaunch_dt_11.png
18. cudalaunch_dt_12.png
19. cudalaunch_dt_14.png
20. cudalaunch_dt_15.png
21. cudalaunch_dt_16.png
22. cudalaunch_dt_17.png
23. cudalaunch_dt_18.png


© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.