

How to Configure Azure Load Balancer for HA Clusters using PowerShell and ARM

https://campus.barracuda.com/doc/96025983/

For incoming traffic to automatically fail over to the secondary HA firewall in case of a failover, you must configure an Azure load balancer. The load balancer has its own public IP address that can be allocated either dynamically or statically. For each service that is made available through the CloudGen Firewall HA cluster, you must create a load balancer rule. At least one health probe must be configured for the load balancer to be able to determine which firewall is currently active. Depending on the probing interval, failover times may vary because the load balancer take several seconds. The load balancer only controls the incoming connections from the Internet. For internal VMs to use the secondary firewall as the default gateway, you must configure UDR routing. <u>How to Configure Azure Route Tables (UDR) using PowerShell and ARM</u> or <u>How to Configure Azure Route Tables (UDR) using Azure Portal and ARM</u>.

Example Load Balancer Deployment Script

You can combine the PowerShell commandlets to customize the deployment of the Azure Load Balancer. See below for an example script. This script assumes that you already deployed your HA cluster and that you are logged in to your Azure Account from the PowerShell.

\$VerbosePreference = 'Continue' \$ErrorActionPreference = 'Stop' \$LBdomainnamelabel = 'YOUR_DOMAIN_LABEL' \$LBResourceGroupName = 'RESOURCE_GROUP_FOR_LOADBALANCER' \$LBPublicIPName = 'NGF-LB-IP' \$LBName =#NGF-LB# \$location = 'West Europe'

\$nic1Name = 'DOC-NGF1-NIC1' # Name of the NIC on the primary firewall \$nic2Name = 'DOC-NGF2-NIC1' # Name of the NIC on the secondary firewall # Resource Group name the firewalls are in. Adapt the script if the primary and secondary firewall are in different resource groups \$nicResourceGroupName = 'DOC-NGF'

create a new resource group for the load balance New-AzureRmResourceGroup -Name \$LBResourceGroupName -Location \$location

Creae a static public IP
#\$LBpublicIP = New-AzureRmPublicIpAddress -Name #NGF-LB-PIP# ResourceGroupName \$LBResourceGroupName -Location \$location -AllocationMethod
Static -DomainNameLabel \$LBdomainnamelabel



\$LBpublicIP = New-AzureRmPublicIpAddress -Name #NGF-LB-PIP# ResourceGroupName \$LBResourceGroupName -Location \$location -AllocationMethod
Static

Add the public IP address as the frontend IP address
\$LBfrontend = New-AzureRmLoadBalancerFrontendIpConfig -Name #NGF-LB-Frontend#
-PublicIpAddress \$LBpublicIP

Create an address pool for the primary and secondary CloudGen Firewall VM
\$LBbackend= New-AzureRmLoadBalancerBackendAddressPoolConfig -Name #NGF-LBbackend#

Create a probe for each service. \$LBprobe1 = New-AzureRmLoadBalancerProbeConfig -Name #TINA-Probe# -Protocol Tcp -Port 691 -IntervalInSeconds 5 -ProbeCount 2 \$LBprobe2 = New-AzureRmLoadBalancerProbeConfig -Name #SSLVPN-Probe# -Protocol Http -Port 443 -IntervalInSeconds 5 -ProbeCount 2 -RequestPath #/_formauth/login.html#

Create a Load Balancing rules for each service \$LBrule1 = New-AzureRmLoadBalancerRuleConfig -Name #TINA_TCP# -FrontendIpConfiguration \$LBfrontend -BackendAddressPool \$LBbackend -Protocol TCP -FrontendPort 691 -BackendPort 691 -Probe \$LBprobe1 \$LBrule2 = New-AzureRmLoadBalancerRuleConfig -Name #SSLVPN# -FrontendIpConfiguration \$LBfrontend -BackendAddressPool \$LBbackend -Protocol Tcp -FrontendPort 443 -BackendPort 443 -Probe \$LBprobe2 \$LBrule3 = New-AzureRmLoadBalancerRuleConfig -Name #SSH# -FrontendIpConfiguration \$LBfrontend -BackendAddressPool \$LBbackend -Protocol Tcp -FrontendPort 22 -BackendPort 22 -Probe \$LBprobe1

Create the Load Balancer
NOTE: Add the additional probes and load balancer rules as necessary

\$LB = New-AzureRmLoadBalancer -ResourceGroupName \$LBResourceGroupName -Name \$LBName -Location \$location -FrontendIpConfiguration \$LBfrontend -LoadBalancingRule \$LBrule1,\$LBrule2,\$LBrule3 -BackendAddressPool \$LBbackend -Probe \$LBprobe1,\$LBprobe2

Add the NIC of the primary and secondary Barracuda CloudGen Firewall VM to



the load balancer and update the NIC configuration
\$nic1 = Get-AzureRmNetworkInterface -ResourceGroupName \$nicResourceGroupName
-Name \$nic1Name
\$nic2 = Get-AzureRmNetworkInterface -ResourceGroupName \$nicResourceGroupName
-Name \$nic2Name
\$nic1.IpConfigurations[0].LoadBalancerBackendAddressPools.Add(\$LB.BackendAddr
essPools[0]);
\$nic2.IpConfigurations[0].LoadBalancerBackendAddressPools.Add(\$LB.BackendAddr
essPools[0]);
\$nic1 | Set-AzureRmNetworkInterface
\$nic2 | Set-AzureRmNetworkInterface

Before You Begin

- Look up the resource group and NIC name for the primary and secondary firewall.
- Install Azure PowerShell version 2.0.1 or higher.

Step 1. (optional) Create a Resource Group for the Load Balancer

Create a resource group for the load balancer, or add it to an existing resource group.

- 1. Open Azure PowerShell.
- 2. Create a resource group:

New-AzureRmResourceGroup -Name NETWORK_RESOURCE_GROUP_NAME -Location YOUR LOCATION

Step 2. Create a Public IP Address for the Load Balancer

The public IP address that is associated with the load balancer can either be allocated dynamically, or configured to be static. You can also add a DNS label and reverse domain lookup.

- 1. Open Azure PowerShell.
- 2. Create a static Azure Public IP. The domain name label is optional.

```
$PublicLoadBalancerIP = New-AzureRmPublicIpAddress -ResourceGroupName
RESOURCE_GROUP_NAME -Location LOCATION -Name PUBLIC_IP_NAME -
DomainNameLabel DOMAIN_NAME -AllocationMethod Static
```



Step 3. Create the Load Balancer Configuration

Create the configuration for the load balancer backend and frontend.

- 1. Open Azure PowerShell.
- 2. Create frontend and backend address pool configurations:

```
$LBfrontend = New-AzureRmLoadBalancerFrontendIpConfig -Name
LB_FRONTEND_NAME -PublicIpAddress $PublicLoadBalancerIP
$LBbackend = New-AzureRmLoadBalancerBackendAddressPoolConfig -Name
LB_BACKEND_NAME
```

Step 4. Create the Load Balancer Rules

For each service, create a rule for the load balancer. Select one service and create the health monitor probe. When the probe fails, the VM is removed from the load balancer backend pool.

- 1. Open Azure PowerShell.
- 2. Create the health probes used to decide whether a service is healthy:

```
$LBprobe1 = New-AzureRmLoadBalancerProbeConfig -Name #LB-Probe# -
Protocol Tcp -Port 691 -IntervalInSeconds 5 -ProbeCount 2
$LBprobe2 = New-AzureRmLoadBalancerProbeConfig -Name #SSLVPN-LB-Probe# -
Protocol Tcp -Port 443 -IntervalInSeconds 5 -ProbeCount 2
```

3. For each service, create a load balancer rule and, optionally, a load balancer probe:

```
$LBrule1 = New-AzureRmLoadBalancerRuleConfig -Name #TINA-TCP# -
FrontendIpConfiguration $LBfrontend -BackendAddressPool $LBbackend -
Protocol Tcp -FrontendPort 691 -BackendPort 691 -Probe $LBprobe1
```

\$LBrule2 = New-AzureRmLoadBalancerRuleConfig -Name #SSL-VPN# FrontendIpConfiguration \$LBfrontend -BackendAddressPool \$LBbackend Protocol Tcp -FrontendPort 443 -BackendPort 443 -Probe \$LBprobe2

Step 5. Create the Azure Load Balancer

Use the configuration and the rules from steps 3 and 4 to create the load balancer.



- 1. Open Azure PowerShell.
- 2. Create the load balancer with the frontend and backend configuration as well as the commaseparated lists for the Loadbalancer rules created in steps 3 and 4:

```
$LB = New-AzureRmLoadBalancer -ResourceGroupName $LBResourceGroupName -
Name $LBName -Location $location -FrontendIpConfiguration $LBfrontend -
LoadBalancingRule $LBrule1,$LBrule2 -BackendAddressPool $LBbackend -
Probe $LBprobe1,$LBprobe2
```

Step 6. Add the NICs to the Load Balancer Backend Pool

- 1. Open Azure PowerShell.
- 2. Store both NICs you want to add to variables:

```
$nic1 = Get-AzureRmNetworkInterface -ResourceGroupName
NGF_RESOURCE_GROUP -Name NIC1_NAME
$nic2 = Get-AzureRmNetworkInterface -ResourceGroupName
NGF_RESOURCE_GROUP -Name NIC2_NAME
```

3. Add the NICs to the backend pool and update the NIC configuration:

```
$nic1.IpConfigurations[0].LoadBalancerBackendAddressPools.Add($LB.Backen
dAddressPools[0]);
$nic2.IpConfigurations[0].LoadBalancerBackendAddressPools.Add($LB.Backen
dAddressPools[0]);
```

\$nic1 | Set-AzureRmNetworkInterface \$nic2 | Set-AzureRmNetworkInterface

Barracuda CloudGen Firewall



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.