


## How to Configure BGP Routing over TINA VPN

<https://campus.barracuda.com/doc/43846863/>

To dynamically learn BGP propagated routes from a remote location connected via TINA VPN tunnel, VPN next hop interfaces are used to create an intermediary network. The BGP service is configured to use the remote IP address in the intermediary network as a BGP neighbor.



You must complete this configuration on both the local and the remote Barracuda NG Firewall using the respective values below:

	Example Values for the Local Barracuda NG Firewall	Example Values for the Remote Barracuda NG Firewall
<b>VPN Next Hop Interface Index</b>	11	11
<b>VPN Next Hop Interface IP Address</b>	192.168.21.16/24	192.168.21.17/24
<b>Virtual Server Additional IP</b>	192.168.21.16	192.168.21.17
<b>VPN Local Networks</b>	192.168.21.16	192.168.21.17
<b>VPN Remote Networks</b>	192.168.21.17	192.168.21.16
<b>VPN Interface Index</b>	11	11
<b>ASN</b>	64577	64578
<b>Router ID</b>	192.168.21.16	192.168.21.17
<b>Neighbor IPv4</b>	192.168.21.17	192.168.21.16
<b>Neighbor AS Number</b>	64578	64577
<b>Neighbor Update Source Interface</b>	vpnr11	vpnr11

## In this article:


### Before You Begin

- A free /24 subnet (e.g., 192.168.21.0/24) for the intermediary network is needed.
- You must have or assign private Autonomous system numbers (ASNs) for the remote and local networks. The ASNs can be private if you are not propagating these networks to other public networks.

### Step 1. Add a VPN Next Hop Interface

Add a VPN next hop interface using a /24 subnet (e.g., 192.168.21.0/24).

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > VPN-Service > VPN Settings**.
2. Click **Lock**.
3. In the **Settings** tab, click the **Click here for Server Settings** link. The **Server Settings** window opens.
4. In the **Server Settings** window, click the **Advanced** tab.
5. Next to the **VPN Next Hop Interface Configuration** table, click **Add**.
6. In the **VPN Interface Properties** window, configure the following settings and then click **OK**.
  - In the **VPN Interface Index** field, enter a number between 0 and 999. E.g., 11
  - In the **IP Addresses** field, enter the VPN interface IP address including the subnet. E.g., 192.168.21.16/24 for the local or 192.168.21.17/24 for the remote NG Firewall.



- Click **OK**. The interface is now listed in the **VPN Next Hop Interface Configuration** table.

VPN Next Hop Interface Configuration

VPN Interf...	MTU	IPs	Multicast
vpn11	1398	192.168.21.16/24	

Add...  
Edit...  
Delete

7. In the **Server Settings** window, click **OK**.
8. Click **Send Changes** and **Activate**.

## Step 2. Add the VPN Next Hop Interface IP Address to the Virtual Server Listening IP Addresses

Introduce the IP address of the VPN next hop interface as a virtual server IP address.


1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Server Properties**.
2. Click **Lock**.
3. In the **Additional IP** table, add the IP address of the VPN interface.
4. Click **Send Changes** and **Activate**.

## Step 3. Configure the TINA Site-to-Site VPN Tunnel

Configure a TINA VPN tunnel using the local next hop interface IP address and the VPN next hop interface.

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > VPN-Service > Site to Site**.
2. Click **Lock**.
3. Right-click In the **TINA Tunnels** tab and select **New TINA tunnel**. The **TINA tunnel** window opens.
4. Enter a **Name**.
5. Configure the **Transport, Encryption** and **Authentication** settings as well as the **Local** and **Remote** public IP addresses. For more information, see [How to Create a TINA VPN Tunnel between Barracuda NG Firewalls](#).
6. Use a free IP address or network as **Local** and **Remote Network**. To avoid multiple tunnels using the same local an remote network it is recommended to use the next hop interface IP addresses. E.g., 192.168.21.16 and 192.168.21.17
  - In the **Local Networks** tab, enter the local next hop interface IP address, as **Network Address** and click **Add**. E.g., 192.168.21.16 for the local and 192.168.21.17 for the remote NG Firewall.
  - In the **Remote Networks** tab, enter the remote next hop interface IP address, as


**Network Address** and click **Add**. E.g., 192.168.21.17 for the local and 192.168.21.16 for the remote NG Firewall.



The screenshot shows two side-by-side configuration panels. The left panel, titled 'Local Networks', has tabs for 'Local' and 'Identify'. It includes a 'Call Direction' dropdown set to 'Active', a 'Local Network Scheme' dropdown set to '-explicit-', and a 'Network Address' table with a header 'Addr/Mask' and one row containing '192.168.21.16/32'. Below the table are 'Add' and 'Delete' buttons. The right panel, titled 'Remote Networks', has tabs for 'Remote' and 'Peer Identification'. It includes a 'VPN Interface Index' input field, a 'Remote Network' table with a header 'Addr/Mask' and one row containing '192.168.21.17 OSPF=NO', and 'Add' and 'Delete' buttons. There is also an 'Advertise route' checkbox.

If used for multiple NG Firewalls connecting to a VPN hub, it is recommended to use the IP address of the local and remote VPN next hop interface to avoid using the same **Remote** and **Local networks** for multiple VPN tunnels.

- In the **Remote Networks** tab, enter the **VPN Interface Index** number that you created in the **VPN Interface Configuration** in step 1. E.g. 11



The screenshot shows the 'Remote Networks' configuration panel with the 'Remote' tab selected. The 'VPN Interface Index' input field contains the value '11'. Below it is a 'Remote Network' table with a header 'Addr/Mask' and one row containing '192.168.21.17 OSPF=NO'. There are 'Add' and 'Delete' buttons and an 'Advertise route' checkbox.

- Click **OK**.
- Click **Send Changes** and **Activate**.

## Step 4. Configure the BGP Service

Enable and configure the BGP service. Configure the remote VPN interface IP address as a BGP neighbor to dynamically learn the routes of the neighboring network.

### Step 4.1 Configure which Routes to Propagate into BGP

You can either enter the networks you want to propagate manually or set the **Advertise Route** parameter to **yes** for routes you want propagated.

1. Go to **CONFIGURATION > Configuration Tree > Box > Network**.
2. Click **Lock**.
3. To propagate the management network, set **Advertise Route** to **yes** in the **Management IP and Network** section.

**Management IP and Network**

Interface Name	eth0	<input type="checkbox"/> Other
Management IP (MIP)	10.0.10.88	
Associated Netmask	25-Bit	
Responds to Ping	yes	
Use for NTPd	yes	
Advertise Route	yes	

4. In the left menu click on **Routing**.
5. Double click on the direct attached and gateway routes you want to propagate. The **Routes** window opens.
6. Set **Advertise Route** to **yes** and click **OK**.

**Route Configuration**


Target Network Address	10.17.0.0/16
Route Type	gateway
Interface Name	<input type="checkbox"/> Other
Gateway	10.0.10.1
Route Metric	
Source Address	
Trust Level	Unclassified
Default Gateway	
Advertise Route	yes
Route Origin	User created
Active	yes

7. Click **Send Changes** and **Activate**.

#### Step 4.2 Configure the BGP Router


Enable BGP and use the VPN next hop interface IP address as the Router ID.

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > OSPF-RIP-BGP-Service > OSPF/RIP/BGP Settings**.
2. Click **Lock**.
3. Set **Run BGP Router** to **Yes**.
4. (optional) To learn routes from the remote ASN set **Operation Mode** to **advertise-learn**.
5. Enter the **Router ID**. Typically the VPN next hop interface IP address is used. E.g., 192.168.21.16 for the local or 192.168.21.17 for the remote NG Firewall.



Operational Setup	
Run OSPF Router	no
Run RIP Router	no
Run BGP Router	yes
Hostname	
Operation Mode	advertise-learn
Router ID	192.168.21.16










6. In the left menu, click **BGP Router Setup**.
7. Enter the **AS Number**. E.g., 64577 for the local NG Firewall or 64578 for the remote NG Firewall.
8. Enter the **Terminal Password**. Use this password if you must directly connect to the dynamic routing daemon via command line for debugging purposes.



BGP Router Configuration				
AS Number	64577			
Terminal Password	Current			
	New	*****		
	Confirm	*****		
Strength				

9. To propagate the directly attached and gateway routes configured in Step 1 set **Connected Routes** to **yes**.

**Route Redistribution Configuration**

Kernel Routes	yes		
Static Routes	yes		
Connected Routes	yes		
RIP Routes	no		
OSPF Routes	no		

10. (alternative) To manually enter the networks you want to propagate click **+** in the **Networks** table and enter the network. E.g., 172.16.0.0/24

**Networks**

Name	Network Prefix
DMZ	172.16.0.0/24

11. Click **Send Changes** and **Activate**.

#### Step 4.3. Add a BGP Neighbor

To dynamically learn the routing of the neighboring network, set up a BGP neighbor for the VPN next hop interface.

- In the left menu of the **OSPF/RIP/BGP Settings** page, click **Neighbor Setup IPv4**.
- Click **Lock**.
- Next to the **Neighbors** table, click the plus sign (+) to add a new neighbor.
- Enter a **Name** for the neighbor and click **OK**. The **Neighbors** window opens.
- Configure the following settings in the **Usage and IP** section:
  - Neighbor IPv4**: Enter the remote address for the VPN next hop interface. E.g., 192.168.21.17 for the local NG Firewall or 192.168.21.16 for the remote NG Firewall.
  - OSPF Routing Protocol Usage** – Select **no**.
  - RIP Routing Protocol Usage** – Select **no**.
  - BGP Routing Protocol Usage** – Select **yes**.
- In the **BGP Parameters** section, configure the following settings:
  - AS Number** – Enter the ASN for the remote network. E.g., 64578 for the local NG Firewall or 64577 for the remote NG Firewall.
  - Update Source** – Select **Interface**.
  - Update Source Interface** – Enter the VPN next hop interface in the format: vpnr. E.g., vpnr11

Usage and IP	
Neighbor IPv4	<input type="text" value="192.168.21.17"/>
Active	<input type="text" value="yes"/>
OSPF Routing Protocol Usage	<input type="text" value="no"/>
RIP Routing Protocol Usage	<input type="text" value="no"/>
BGP Routing Protocol Usage	<input type="text" value="yes"/>

OSPF Parameters	
Neighbor Priority	<input type="text"/>
Dead Neighbor Poll Interval	<input type="text"/>

BGP Parameters	
AS Number	<input type="text" value="64578"/>
Description	<input type="text"/>
Peer Group Affiliation	<input type="text"/>
Update Source	<input type="text" value="Interface"/>
Update Source Interface	<input type="text" value="vpn11"/>
Update Source IPv4 Address	<input type="text"/>
Peer Filtering For Input	<input type="button" value="Set..."/> <input type="button" value="Clear"/> NOTSET: No section present
Peer Filtering For Output	<input type="button" value="Set..."/> <input type="button" value="Clear"/> NOTSET: No section present

7. Click **OK**.
8. Click **Send Changes** and **Activate**.

#### Step 4.4. (optional) Adjust Keep Alive and Hold Timer

Speed up BGP updates by adjusting the keep alive and hold timer.

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > OSPF-RIP-BGP-Service > OSPF/RIP/BGP Settings**.
2. Click **Lock**.
3. In the left menu, click on **BGP Router Setup**.
4. In the left menu, expand the **Configuration Mode** section and click on **Switch to Advanced View**.
5. Click the **Edit** button for the **Advanced Settings**. The **Advanced Settings** window opens.



6. Adjust the following parameters to influence how fast BGP reacts to connections which are down:
  - **Keep Alive Timer** - Default: 60 Recommended: 10
  - **Hold Timer** - Set to three times the **Keep Alive Timer**. Default: 180 Recommended: 30
7. Click **OK**.
8. Click **Send Changes** and **Activate**.

## Step 5. Verify the BGP Service Configuration

On the **CONTROL > Network** page, verify that BGP routes are learned. Click the **BGP** tab and expand the relevant AS tree. It can take up to three minutes for new routes to be learned. The **Origin** column lists **incomplete** for direct attached or gateway routes or **IGP** routes learned via BGP including manually entered networks.

Local Firewall **CONTROL > Network > BGP** page:

Network	Next Hop	Metric	Local Pref	Weight	Path	Origin
<b>Local</b>						
> 172.16.0.0/24	0.0.0.0	0		32768	Local	IGP
<b>AS Incomplete</b>						
> 10.0.10.0/25	0.0.0.0	0		32768		Incomplete
> 10.17.0.0/16	10.0.10.1	0		32768		Incomplete
> 10.27.0.0/16	10.0.10.1	0		32768		Incomplete
<b>AS 64580</b>						
<b>AS 64579</b>						
<b>AS 64578</b>						
<b>Neighbor: 192.168.21.17</b>						
Prefixes Received: 1						
Up/Down-Time: 00:06:08						
Sent Messages: 14						
Received Messages: 8						
> 10.0.81.0/24	192.168.21.17	0		0	64578	IGP

Remote Firewall **CONTROL > Network > BGP** page:

Network	Next Hop	Metric	Local Pref	Weight	Path	Origin
<b>Local</b>						
> 10.0.81.0/24	0.0.0.0	0		32768	Local	IGP
<b>AS 64577</b>						
Neighbor: 192.168.21.16						
Prefixes Received: 8						
Up/Down-Time: 00:09:08						
Sent Messages: 349						
Received Messages: 398						
> 10.0.10.0/25	192.168.21.16	0		0	64577	Incomplete
> 10.0.80.0/24	192.168.21.16			0	64577 64579	IGP
> 10.10.10.0/24	192.168.21.16			0	64577 64580	IGP
> 10.10.200.0/24	192.168.21.16			0	64577 64580	IGP
> 10.17.0.0/16	192.168.21.16	0		0	64577	Incomplete
> 10.27.0.0/16	192.168.21.16	0		0	64577	Incomplete
> 172.16.0.0/24	192.168.21.16	0		0	64577	IGP
> 192.168.200.0	192.168.21.16			0	64577 64580	IGP

## Step 6. Create Access Rules for VPN Traffic

Create access rules on both local and remote NG Firewalls to allow traffic from the learned networks through the VPN tunnel.

## Figures

1. BGPOverTINAVPN.png
2. tina\_bgp01.png
3. tina\_bgp02.png
4. tina\_bgp03.png
5. tina\_bgp04.png
6. tina\_bgp06d.png
7. tina\_bgp06c.png
8. tina\_bgp05.png
9. tina\_bgp06a.png
10. tina\_bgp06e.png
11. tina\_bgp06b.png
12. tina\_bgp07.png
13. tina\_bgp08.png
14. tina\_bgp09.png

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.