

How to Configure a Zone

<https://campus.barracuda.com/doc/96026353/>

The CloudGen Firewall offers the option to configure primary, secondary, reverse, and forwarding zones. When configuring a primary or reverse zone, it is important to correctly handle the serial / serial number offset value.

Timestamps are used in the DNS system to synchronize zone transfers. You must be careful when using the CloudGen Firewall as a DNS primary in conjunction with a DNS secondary server running a non-Barracuda Networks product!

The effective serial number is derived from the firewall's Unix time-stamp. In a mixed setup of a CloudGen based DNS primary server and a non-Barracuda DNS secondary server, Unix time-stamps are numerically lower than date-based time-stamps (e.g. 2019043000). Therefore, a serial number offset must be added to the Unix-based time-stamp. The result of this addition must be greater than the date-based time-stamp at the moment of activating the zone's data. Only then will a secondary DNS server accept a zone transfer from the primary.

For converting the current time into a Unix-based time-stamp, you can use a calculator on the Internet, e.g., www.unixtimestamp.com.

Before You Begin

- Verify that all necessary IP addresses for answering DNS queries are already configured as service IP addresses on the respective incoming interfaces. For more information, see [How to Assign Services](#).
- Ensure that the serial number offset is high enough.

Option 1: Configure a Primary Zone


1. Go to **CONFIGURATION > Configuration Tree > Box > Assigned Services > DNS > DNS-Service**.
2. In the left menu, click **Hosted Zones**.
3. Right-click in the window.
4. From the list, select **Add new DNS Zone**.
5. The **Add Hosted Zone / Domain window** is displayed.
6. For **Hosted Zone Type**, select **Primary**.
7. For **Enabled**, select the check box if you want the record to be active.
8. For **Domain Name**, enter the name of the domain, e.g., `example.com`.

Because the underscore character ('_') is not processed correctly by the underlying BIND

system, do not use this character when you enter domain names!

While entering the domain name, the edit field for Authoritative Name Server will be auto-filled and the standard name ns1 will be prepended to your domain name for the name server.

9. For **Description**, enter any text that best describes your domain.
10. **TTL** (time to live [sec]) is already preset. Change the value if necessary.
11. For **Serial Number Offset**, enter the offset only if the serial of your new zone record must be higher than the serial on the secondary DNS server.
12. For the auto-filled edit field **Authoritative Name Server** you can omit any changes unless necessarily required.
13. For **Responsible Person Email**, enter the email address of the person that is responsible for the configured domain. The edit field accepts the underscore character: '_'.
14. Select **Generate NS Record** if you want to have the name server record created automatically for you.
15. For **Zone Transfer**, select **Yes** if you want to allow automatic zone transfers.
16. For **Zone Transfer ACL**, enter all IP addresses of secondary DNS servers that are allowed to exchange zone data with the primary.
17. Click **OK**.
18. Click **Send Changes**.
19. Click **Activate**.



Edit Hosted Zone / Domain standalone.org

Hosted Zone Type: **Primary**

Enabled: ☒

Domain Name: **standalone.org**

Description:

TTL: **86400**

Serial Number Offset: **0**

Authoritative Name Server: **ns1.standalone.org**

Responsible Person Email: **root@standalone.org**

Generate NS Record: ☒

Zone Transfers: **Yes**

Zone Transfer ACL: **5.5.5.239, 6.6.6.239**

Hosted Zone Type
The type of the zone to be configured for hosting.

Enabled
In case you are operating a primary and secondary DNS, verify that the zone status is in sync on both domain name servers.

Domain Name
The full qualified domain name (FQDN) for the domain to be hosted.

Description
Descriptive information for the domain.

TTL
Sets the time after which the record is regarded to be invalid.

Serial Number Offset
The serial number offset is used for managing the newest zone data after zone transfers between DNS servers.

Authoritative Name Server
The name of the primary name server responsible for the referred domain in the edit field Domain Name.

Responsible Person Email
Specifies the mailbox of the person responsible for a host (domain name).

Generate NS Record
Tick this checkbox so that the firewall will automatically generate the respective NS record.

Zone Transfers
Set to 'Yes' so that the firewall will do zone transfers automatically.

Zone Transfer ACL
Configure DNS server(s) that is (are) allowed to exchange zone data with this DNS server by entering either an IP address or an IP mask.

OK **Cancel**


You have now configured a primary zone.

Domain	Zone Status	Type	Owner	TTL	Email	Record Data	Description
standalone.org (Primary)	Enabled			86400	root@standalone.org		
		NS	@	3600		ns1.standalone.org	Automatically generated
		A	ns1	3600		3.3.3.238, 4.4.4.238	Automatically generated
		A	ns2	3600		5.5.5.239, 6.6.6.239	

Option 2: Configure a Secondary Zone

If your firewall must operate as a secondary DNS server for a certain zone hosted on another authoritative primary DNS server, create a secondary zone to host it on your firewall.

1. Go to **CONFIGURATION > Configuration Tree > Box > Assigned Services > DNS > DNS-Service**.
2. In the left menu, click **Hosted Zones**.
3. Right-click in the window.
4. From the list, select **Add new DNS Zone**.
5. The **Add Hosted Zone / Domain window** is displayed.
6. For **Hosted Zone Type**, select **Secondary**.
7. For **Enabled**, select the check box if you want the record to be active.
8. For **Domain Name**, enter the domain for which you want to create a secondary zone, e.g., `example2.com`.
9. For **Description**, enter any text that best describes your domain.
10. Click **+** to add the primary DNS server that hosts the primary zone.
11. The **Add New Key** window is displayed.
12. Enter the IP address for the primary DNS server, e.g., `212.86.0.11`, where to make the zone transfer from.
13. Click **OK**.
14. Click **Send Changes**.
15. Click **Activate**.



In the **Hosted Zones** window, you can now see the record for the primary zone

example2.com (Slave)		1d	No	Description for domain example2.com
----------------------	--	----	----	-------------------------------------

Because a secondary zone is managed by its owning primary server, no records will be shown on the secondary DNS server.

Option 3: Configure a Reverse Zone

Configuring a reverse zone requires a primary zone that is already configured. If there is no primary zone configured yet, start over with **Option 1** above.

1. Go to **CONFIGURATION > Configuration Tree > Box > Assigned Services > DNS > DNS-Service**.
2. In the left menu, click **Hosted Zones**.
3. Right-click in the window.
4. From the list, select **Add new DNS Zone**.
5. The **Add Hosted Zone / Domain window** is displayed.
6. For **Hosted Zone Type**, select **Reverse**.
7. For **Enabled**, select the check box if you want the record to be active.
8. In the edit field **Network** at the bottom of the window, enter the network address that you are configuring the reverse zone for, e.g., 62.99.0.0/24.
9. The edit field for **Domain Name** will be auto-filled based on the network address.
10. For **Description**, enter any text that best describes your domain.
11. **TTL** (time to live [sec]) is already preset. Change the value if necessary.
12. For **Serial Number Offset**, enter the offset only if the serial of your new zone record must be higher than the serial on the secondary DNS server.
13. For **Authoritative Name Server**, enter the same name server as for the related primary zone, e.g., ns1.example.com.
14. For **Responsible Person Email**, enter the email address of the person that is responsible for the configured domain.
15. For **Zone Transfer**, select **Yes** if you want to allow automatic zone transfers.
16. For **Zone Transfer ACL**, enter all IP addresses of secondary DNS servers that are allowed to exchange zone data with the primary.
17. Click **OK**.
18. Click **Send Changes**.
19. Click **Activate**.

Edit Hosted Zone / Domain 30.0.99.62.in-addr.arpa

Hosted Zone Type

Enabled
☒

Domain Name

Description

TTL

Serial Number Offset

Primary Master Name Server

Responsible Person Email

Generate NS Record
☐

Zone Transfers

Zone Transfer ACL

Network

Hosted Zone Type
The type of the zone to be configured for hosting.

Domain Name
The full qualified domain name (FQDN) for the domain to be hosted.

Description
Descriptive information for the domain.

TTL
Sets the time after which the record is regarded to be invalid.

Serial Number Offset
The Serial number offset is used for managing the newest zone data after zone transfers between DNS servers.

Primary Master Name Server
The name of the master name server responsible for the referred domain in the edit field Domain Name, also known as the authoritative nameserver.

Responsible Person Email
Specifies the mailbox of the person responsible for a host (domain name).

Generate NS Record
Tick this checkbox so that the firewall will automatically generate the respective NS record.

Zone Transfers
Set to 'Yes' so that the firewall will do zone transfers automatically.

Zone Transfer ACL
Configure DNS server(s) that is (are) allowed to exchange zone data with this DNS server by entering either an IP address or an IP mask.

Network
Enter the network address for which the reverse entry shall be automatically generated, e.g., 172.16.0.0/24.

In the **Hosted Zones** window, you can now see the record for the reverse zone.

0.99.62.in-addr.arpa (Reverse)		86400	root@example.com	No	Reverse Zone for example.com
--------------------------------	--	-------	------------------	----	------------------------------


Option 4: Configure a Forward Zone

If your firewall must operate as a secondary DNS server for a certain zone hosted on another authoritative primary DNS server, create a secondary zone to host it on your firewall.

1. Go to **CONFIGURATION > Configuration Tree > Box > Assigned Services > DNS > DNS-Service**.
2. In the left menu, click **Hosted Zones**.
3. Right-click in the window.
4. From the list, select **Add new DNS Zone**.
5. The **Add Hosted Zone / Domain window** is displayed.
6. For **Hosted Zone Type**, select **Forward**.
7. For **Enabled**, select the check box if you want the record to be active.
8. For **Domain Name**, enter the domain for which you want to create a forwarder, e.g., `example.com`.
9. For **Description**, enter any text that best describes your domain.
10. Click **+** to add a DNS forwarder.
11. The **Add New Key** window is displayed.
12. Enter the IP address for the DNS forwarder, e.g., `212.86.0.11`.
13. Click **OK**.

14. Click **Send Changes**.

15. Click **Activate**.



Add Hosted Zone / Domain

Hosted Zone Type: **Forward**

Enabled: ☒

Domain Name: **example.com**

Description: **Description for domain example.com**

DNS Forwarders: **212.86.0.11**

Hosted Zone Type
The type of the zone to be configured for hosting.

Enabled
In case you are operating a primary and secondary DNS, verify that the zone status is in sync on both domain name servers.

Domain Name
The full qualified domain name (FQDN) for the domain to be hosted.

Description
Descriptive information for the domain.

DNS Forwarders
Enter the IP address of DNS servers responsible for queries for the given domain.

OK **Cancel**

Figures

1. add_master_zone_window.png
2. master_zone_record.png
3. add_slave_zone_window.png
4. slave_zone_record2.png
5. reverse.PNG
6. reverse_zone_record2.png
7. add_forward_zone.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.