

## Domain Admin Role

<https://campus.barracuda.com/doc/3866690/>

The Domain Admin role is available on the Barracuda Email Security Gateway 600 and above and can configure all domain settings for designated domains as well as account settings for account holders who have lesser permissions. This role includes **Helpdesk** level permissions and use cases as described above plus the ability to:

- View message contents (if privacy settings allow) for designated domains.
- Enable or disable per-user quarantine at the domain level and, if per-user quarantine is disabled, specify a global quarantine email address for designated domains.
- Enable or disable various **Default User Features** for new accounts (see [Controlling Access to Account Features](#)) for designated domains.


### Domain Admin Role - All\_Domains Permissions

The Domain Admin role has the above permissions for ALL domains configured on the Barracuda Email Security Gateway if the **Managed domains for** text box on the **USERS > Account View > Edit Role** page for this account holder includes the phrase "all\_domains". In this case, all domains for which the Barracuda Email Security Gateway filters email will appear in the **DOMAINS** page.

- A Domain Admin account holder with **all\_domains** permission can also do the following:
- Create or change the role of a **Domain Admin** account holder who does not have **all\_domains** permissions.
- Log into and manage the quarantine inbox of a **Domain Admin** who does not have **all\_domains** permissions.
- Create or edit a **Helpdesk** account with all\_domains permissions.

Navigation of the web interface for the **Domain Admin** role follows the examples illustrated for the [Helpdesk Role](#), plus the following.

**Figure 1: The *Domain Admin* role can configure domain-level settings.**



**Barracuda | Email Security Gateway**

domainadmin1@barracuda.com [test.com] Sign out English

Manage Domains Manage Account

**BASIC** BLOCK/ACCEPT USERS ADVANCED OUTBOUND QUARANTINE

Status Message Log Spam Checking Virus Checking Quarantine **IP Configuration** Reports

Links enable return to the DOMAINS page or managing personal account Save Cancel

### DESTINATION MAIL SERVER TCP/IP CONFIGURATION Help

Destination Server:  Dest. Port:

The IP address or hostname of your SMTP Host and the TCP Port. Recommended: 25

Valid Test Email Address:  Test SMTP Connection

Use MX Records: ☒ Yes ☐ No

Set to Yes if the Destination Server listed above is actually a domain and mail should be forwarded to the appropriate MX records. If Yes, you must enter a domain for the Destination Server. Recommended: No

## Figures

### 1. DomainAdminIPConfigBESG.jpg

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.