
How to Uninstall the Barracuda VPN Client for Linux

<https://campus.barracuda.com/doc/46206599/>

Uninstall the Barracuda VPN Client for Linux or the macOS command line according to the instructions given in the section for your operating system. To remove the Barracuda VPN Client for Linux or the macOS command line, you must uninstall the Barracuda VPN Client as root. For Windows and macOS GUI versions, see [How to Uninstall the Barracuda NAC/VPN Client for Windows](#) and [How to Uninstall the Barracuda VPN Client for macOS](#).

Before You Begin

Before uninstalling the Barracuda VPN Client for Linux, terminate any established VPN connections.

Uninstall the Barracuda VPN Client for RPM package-based Linux

1. Open a command-line window.
2. To uninstall the Barracuda VPN Client, enter: `rpm -e barracudavpn`
3. (Optional) To remove any certificates and licenses, enter: `rm -rf /etc/barracudavpn`

Uninstall the Barracuda VPN Client for Debian

1. Open a command-line window.
2. To uninstall the Barracuda VPN Client, enter: `dpkg -r barracudavpn`
3. (Optional) To remove any certificates and licenses, enter: `rm -rf /etc/barracudavpn`

Uninstall the Barracuda VPN Client for FreeBSD

1. Open a command-line window.
2. To uninstall the Barracuda VPN Client, enter: `pkg_delete barracudaVPN-2.0-SP2`
3. (Optional) To remove any certificates and licenses, enter `rm -rf /etc/barracudavpn`

Uninstall the Barracuda VPN Client for macOS

1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
2. Open a command-line window.

3. To uninstall the Barracuda VPN Client, enter: `rm /usr/local/bin/barracudavpn`
4. (Optional) To remove any certificates and licenses, enter: `rm -rf /System/Library/barracudavpn`

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.