

How to Export VPN Files for VPN Group Policies


<https://campus.barracuda.com/doc/73719143/>

To export the settings of the client-to-site VPN for your Barracuda VPN or Network Access Client, you must export a vpn file. The vpn file can be exported for both personal license and VPN group policy VPN configurations.


Download VPN File from VPN Group Policy

Download the VPN template (*.vpn) file from the client-to-site configuration.


1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > VPN-Service > Client-to-Site**.
2. Click the **External CA** tab.
3. In the **Group Policy** tab, double-click on the VPN group policy. The **Edit Group Policy** window opens.



4. Click **Export to file**. The **Export VPN Profile** window opens.




5. Enter a new **Description**.
6. Enter the IP address of the **VPN Server**.
7. Click **OK**.




Download VPN File from Personal License Configuration

1. Go to **CONFIGURATION > Configuration Tree > Box > Virtual Servers > your virtual server > Assigned Services > VPN-Service > Client-to-Site**.
2. In the **Barracuda VPN CA** tab, double-click on the personal license you want to export.
3. Click **Export to File** and click **Export to .vpn file**. The **Export VPN Profile** window opens.



4. Enter a **Description**. This is the name of the imported VPN profile in the VPN client.
5. Scroll down to the **VPN Server** entry and enter the public IP address the client uses to connect to the VPN service.



The image shows a dialog box titled "Export VPN Profile" with a close button (X) in the top right corner. The "Description" field contains the text "MyVPNConnection". Below this is a table of configuration options:

Prompt for credentials	No
Remember User name	No
Transport Mode	Reliability (TCP)
Use Access Control Service	No
Use MS Credential Manager	No
VPN Server	62.99.0.40
Virtual Adapter Configuration IPv4	Direct assignment

At the bottom of the dialog are "OK" and "Cancel" buttons.

Next Step

Double-click on the vpn file to import it into the Barracuda VPN or Network Access Client.

For more information, see [Remote Access Clients](#).

Figures

1. vpnfiles00.png
2. vpnfiles01.png
3. vpnfiles02.png
4. personal_license_VPN_file_01.png
5. personal_license_VPN_file_02.png

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.