

## How to Manually Install Updates via Barracuda Firewall Admin

<https://campus.barracuda.com/doc/79463385/>

If you are updating a firewall or Control Center that does not have direct Internet access to download updates and hotfixes from the Barracuda Download Portal, use the browser on the client running Barracuda Firewall Admin to download the packages from the Barracuda Networks download portal. You can then upload and install the update packages manually with the **Install Update** feature in Barracuda Firewall Admin.


### Step 1. Download the Update from the Barracuda Download Portal

Go to the [Barracuda Networks download portal](#) and download the update or hotfix. For more information, see [How to Download Applications, Updates, and Hotfixes](#).

### Step 2. Install the Update with Barracuda Firewall Admin

Upload and activate the update using Barracuda Firewall Admin.

1. Go to **CONTROL > Box**.
2. In the left menu, expand the **Operating System** section and click **Install Update**.



The screenshot displays the Barracuda Firewall Admin interface. On the left, a navigation menu is visible with the following sections: 'Time', 'Network', 'Dynamic Networks', and 'Operating System'. The 'Operating System' section is expanded, showing options: 'Reboot Box', 'Firmware Restart', 'Shutdown Box', 'Manage via Web Interface', 'Save current Config for ART', 'Install Update' (highlighted with a red box), 'Generate System Report', and 'Reset SMS Counter'. The main content area on the right shows a 'Report' section with a 'Copy Report to Clipboard' button.

3. Select the update file and click **Open**.

Update in progress. Do not turn off your firewall.

Uploading update.GWAY-8.0.1-056.nightbuild.tgz ...




262008 KB of 619677 KB (42.3%) remaining about 1 min

Install update after upload.

Cancel Upload

4. Click **Yes** to start the update.



5. Wait for the update to finish.

Update in progress. Do not turn off your firewall.

Installing update.GWAY-8.0.1-056.nightbuild.tgz ...

Your unit reboots after the update is finished.

## Figures

1. 801\_Update\_install01.png
2. 801\_Update\_install02.png
3. 801\_Update\_install03.png
4. 801\_Update\_install04.png

© Barracuda Networks Inc., 2022 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.