

Configuring Custom IP List

<https://campus.barracuda.com/doc/79465548/>

Overview

Use this section to upload/download a Custom IP List text file to the Barracuda Web Application Firewall.

To add more IP addresses to the current list, upload a new file that contains both the existing and the newly added IP addresses list. Once you upload the new file, the current list is overwritten with the new list. It is recommended to save a local copy of this file because you cannot view the contents of the file after you upload it.

This feature is supported ONLY on Network Layer IP Reputation.

- Before you upload/download a Custom IP List text file, set **Advanced Settings** to **Yes** on the **ADVANCED > System Configuration** page .
- Ensure that every IP address in the text file is provided in a new line.
- CIDR notation is not supported.

Upload a Custom IP List Text File

Upload the Custom IP List text file to the Barracuda Web Application Firewall.

1. Navigate to **WEBSITES > IP Reputation > Custom IP List**.
2. Click the **Upload** option from the **Custom IP List** field.
3. Click **Browse** and select the text file that contains the list of block-listed IPs. The URL of the selected text file is listed in the **Upload File of Blocklisted IPs** text box.
4. Click **Upload Now** to upload the text file to the Barracuda Web Application Firewall.

Download a Custom IP List Text File

Download a Custom IP List text file to the Barracuda Web Application Firewall.

1. Click the **Download** option from the **Custom IP List** field.

2. In the **Download URL** text box, enter the URL of the text file present on the server.
The URL of the Custom IP List does not support HTTP.
3. Select **Yes** from the **Validate Server Certificate** field to validate the server certificate.
4. Click the **Trusted Certificate** drop-down list and select the certificate that must be validated against the server.
5. Click **Download**. The text file that contains the list of block-listed IP addresses is downloaded to the Barracuda Web Application Firewall.

You can open the downloaded text file and view the IP list.

Modify a Custom List Text File

To modify an uploaded custom IP list, perform the following steps:

1. Download the custom list text file.
2. Open the text file, add or remove the IP addresses and save the file.
3. Re-upload the updated custom list file.

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.