

## Viewing the Assessment Results for Different Security Schemas

<https://campus.barracuda.com/doc/90441769/>

The Security Schema that a user sees by default is determined by what Security Schemas are available and what permissions the user has. The following table shows which Security Schema a user sees on the **Site Security Dashboards** by default:

Has a custom Security Schema been applied to the site?	Does the user have permissions to switch between Security Schemas?	What Security Schema does the user see by default?
No	No	<b>Standard</b>
Yes	No	Custom Security Schema
Yes	Yes	Custom Security Schema

If a user has permission to switch between Security Schemas and there is a custom Security Schema applied to the site, the user sees the custom Security Schema by default. However, since they have permission to view custom Security Schemas, they can also toggle to the Standard Security Schema for easy scoring comparisons.

### To Switch the Dashboard Between a Custom Security Schema and the Standard Security Schema

Users with the correct permissions can switch between viewing the scores from the custom Security Schemas and the scores from the Standard Security Schema. By default, the roles with this permission are:

- **Administrator**
- **Technician**

When a user changes the Security Schema that is displayed on their dashboard, the Security Schema applied to the site doesn't change, and both Security Schemas are still assessed. This procedure only switches the user's view.

For example, if a user switches from a custom Security Schema to view the Standard Security Schema, the custom Security Schema is still used for the assessment.

1. In Service Center, click **Dashboards > Site Security Dashboard**.
2. Click a site link.
3. Click **Site Scores**, then click a **Security Schema**.

Users with the correct permissions can also switch between Security Schemas on a site's **Security Details** page. Click **Dashboards > Site Security Dashboard**, then click a site link. Then click **Site Scores**, then a **Security Schema**.

© Barracuda Networks Inc., 2021 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.