

## Download Barracuda Managed Workplace 12 Service Pack 1 Maintenance Release 1 - Self-hosted

<https://campus.barracuda.com/doc/91981128/>

Use these files if you host your own Service Center.

Make sure you follow the correct process for your upgrade or new installation by following the steps we've outlined here. You can upgrade to Barracuda Managed Workplace 12 SP1 MR1 from Managed Workplace 12 SP1 or higher.

Once you have upgraded to Barracuda Managed Workplace 12 SP1 MR1, download [HotFix 2](#) from the Upgrade Center

Thorough preparation is the key to any successful project on production servers.

### Steps to Upgrade to 12 SP1 MR1

#### Before you begin

First and most importantly, **back up your database** .

Take a moment to review the [Release Notes - 12 SP1 MR1](#).

#### Prerequisites

The Barracuda Managed Workplace installer will not allow you to proceed if you do not have the correct software configuration in place.

As an example, the Barracuda Managed Workplace install engine will abort your upgrade if it determines that Windows SQL 2008 Service Pack 1 has not been applied.

If you are using a self-hosted version of Barracuda Managed Workplace, before upgrading to Barracuda Managed Workplace 10 or higher, it is **highly recommended** that you set the **Max Degree of Parallelism** setting in the SQL **Server Properties** window. Enabling this setting improves SQL performance during and after the upgrade.

To set the Max Degree of Parallelism setting, perform the following steps:

1. In the SQL **Server Properties** window, click the **Advanced** page.
2. In the **Parallelism** area, for **the Max Degree of Parallelism** setting, enter 1. By default, this is set to 0.

If you are manually upgrading an Onsite Manager installed to a SQL instance other than LPIMWOMEXPRESS, please contact Support for assistance with moving your database to an instance using this name. Remote upgrades to Onsite Managers will continue to upgrade other instances without issue.

Barracuda Managed Workplace 12 SP1 MR1 requires .NET 4.6.0 or higher. If you do not have .NET 4.6.0 or higher installed, it will be installed as part of Barracuda Managed Workplace, which may require a restart. Please see "Reboot After Install" in the Barracuda Managed Workplace Setup Guide for details.

We invite you to **assess your current infrastructure** against the recommendations for Barracuda Managed Workplace:

- [Barracuda Managed Workplace 12 SP1 MR1 Setup Guide - On Premise](#)

## Begin the Download

**Backup your database** (if you haven't already done so).

Download the Barracuda Managed Workplace software:

- [Service Center MW12 SP1 MR1 Installer](#)
- [Onsite Manager MW12 SP1 MR1](#)

After downloading the installation package, you ensure the zip file is not blocked by right-clicking the file, selecting **Properties**, and then selecting Unblock. Additionally, after extracting the files, you run the setup with elevated privileges, such as **Run as Administrator**.

**After installing Barracuda Managed Workplace 12 SP1 MR1, visit the Update Center to install Barracuda Managed Workplace 12 SP1 MR1 HotFix 2. Review the [HotFix readme](#).**

You can upgrade to Barracuda Managed Workplace 12 SP1 MR 1 from Barracuda Managed Workplace 12 SP1 or higher. The link may be found below:

- [Service Center MW12 SP1 Installer](#)
- [Onsite Manager MW12 SP1](#)

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.