

Getting Started

https://campus.barracuda.com/doc/93201507/

The following configuration steps will allow you to access a resource protected by the CloudGen Access Proxy.

Before You Begin

- The CloudGen Access Proxy is the software that contains the Envoy Proxy and the CloudGen Access Proxy Orchestrator.
- The Envoy Proxy listens to requests and proxies them to the correct destination.
- The CloudGen Access Proxy Orchestrator ensures that the Envoy Proxy is configured with the correct requests and manages authorization and authentication requests. This requires a valid token (CloudGen Access Proxy enrollment link) that contains the necessary information to bootstrap and authorize the service.

Step 1. Add a New CloudGen Access Proxy

- 1. Go to:
 - 1. <u>CloudGen Access Enterprise Console US</u> OR -
 - 2. <u>CloudGen Access Enterprise Console EU</u>
- 2. Navigate to Access and then Proxies.
- 3. Click the + icon in the top right.

This proxy will be used to test access for the test resource. However, this does not prevent it from being used as a permanent proxy later on.



Overview	Resources 83 Proxies 7 Policies	s 6			
O Identity					Ŧ
Access	☐ Name Location Proxy Host:Port	Resources	Accesses	Last Access	
DNS Security	AWS US West	2	65	1 day ago	Ø
Activity	Azure vNet	2	27	1 day ago	Ø
	L K8S Dev	14	257	about 19 hours ago	Ø
දිංිිි Settings	K8S Prod	12	1643	about 2 hours ago	Ø
	K8S Stg	3	0	-	Ø
	K8S Test Prod	1	26	12 days ago	Ø

- 4. Add the following:
 - **Proxy Name** Used to identify the proxy.
 - **Location** (optional) For your reference only.
 - **Host** IP/Hostname used to reach the proxy.
 - **Port** Port where the CloudGen Access Proxy will be available.
- 5. Click **Create**.



		€ enterprise.fyde.com Č			ÔÓ
<	Access > Proxies				
Overview		Proxies 7 Policies 6			
A Identity		Proxy Configuration			Ŧ
Access	Name Lo		Accesses	Last Access	
DNS Security	AWS US Or West	Proxy Name *	65	1 day ago	
Activity	Azure We vNet We	Location	27	1 day ago	
	K8S Ku Dev EU	Host *	257	about 19 hours ago	
တ္သိ Settings	K8S Ku Prod US	Port *	1643	about 2 hours ago	
	K8S Stg Ku US				
		Cancel Create			
ņ					

Copy the link that will be used when configuring the proxy.
This is the only time the link is provided by the Management Console.

		i enterprise.fyde.com			
<	Access > Proxies				
Overview	Resources 83	Proxies 8 Policies 6			
O Identity		Proxy Configuration			Ð
Access	Name Lo	This is the only time that the secret access keys can be viewed or downloaded. You cannot recover it later. However, you can create new access keys at any time. Proxy was successfully created.	Accesses	Last Access	
DNS Security	AWS US Or West		65	1 day ago	
Activity	Azure We	Please copy the link to integrate with other systems. We are almost done.	27	1 day ago	
: / Kettivity	K8S Ku Dev EU		257	about 19 hours ago	
ŵ Settings	K8S Ku Prod US	Link:	1643	about 2 hours ago	
	K8S Stg Ku				
	🗌 test tes				
		Ok			
_					F
Q					



Step 2. Install the CloudGen Access Proxy in Docker

In this quick start guide, we recommend installing the solution using the docker infrastructure. For other platforms, such as <u>Bare Metal / Virtual Machine</u>, see <u>How to Deploy the CloudGen Access Proxy</u>.

- The public port will need to be available for the clients connecting to resources.
- The required images are available in dockerhub registry under the organization <u>FydeInc</u>.
- Requires a valid CloudGen Access Proxy enrollment link, obtained in the previous step.

Minimum OS supported versions:

- Debian 9
- Centos 7
- Ubuntu 16.04
- MacOS 10.14

Please note that the steps below will execute scripts obtained externally. We advise you to inspect the content before execution.

- 1. Choose **yes**, when asked about installing the test resource.
- 2. Download and execute installation script.

sudo bash -c "\$(curl -fsSL https://url.access.barracuda.com/proxy-docker)"

Step 3. Add a New Resource

See the <u>Add Resource</u> article and use the following test values:

• Resource Type - Select Self-hosted:

- Resource Name HTTP Test
- **Proxy** Select the existing CloudGen Access Proxy.
- Public Host http.example.org
- Internal Host Internal resource hostname or IP used by the CloudGen Access Proxy to connect to. Needs to be a hostname or IP that the CloudGen Access Proxy can resolve and connect to.
- Assign Fixed IP If enabled, assigns a fixed IP address to the resource, and the resource domain will always be resolved to that IP address on the client side
- Ports Configuration Click Add New to add ports to allow for this resource. You can add ports as a single number or a range (e.g. 80 or 1000-1050). Note that the size of the public port and internal port ranges must be the same.



- Access Policies Assign an existing policy to Allow Everyone to log into this resource.
- SSO Configuration See SSO Configuration in the Resource Type Selfhosted: section in the <u>Add Resource</u> article.
- Notes Leave empty.

Step 4. Add a New User

In order to register a device, you need to create a user. Users and account administrators are separate entities. The same email can be used for account administrators and a regular user, and there will be no relation between them.

To add a new user, follow instructions for Add User.

Step 5. Enroll a Device

A user can have multiple devices. This is determined by the account administrators.

- 1. Enroll a new device for the created user by accessing the enrollment link.
- 2. The link is sent to the email configured for the user or by sharing the link from the user details.
- 3. The enrollment process is done directly from the created user's device.

Step 6. Access Created Resource

The enrolled device will now access the created resource. Access the configured resource by visiting the following link from the enrolled device: *http://http.example.org:81/*

Troubleshooting

If the device is not accessing the resource, see <u>Troubleshooting the CloudGen Access Proxy</u> for troubleshooting steps.

Barracuda CloudGen Access



Figures

- 1. ec-access-proxies.png
- 2. ec-access-add-proxy.png
- 3. ec-access-add-proxy2.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.