


## How to Configure Custom OIDC Authentication

<https://campus.barracuda.com/doc/93201543/>

### Configure OIDC

1. Go to **Identity > Settings**.
2. In the **Authentication Protocol** section, click **Activate Provider**.
3. Click on your OpenID Connect choice.



**Authentication protocol**

**Identity provider**

This setting enables enforcement of authentication for all users when enrolling a new device and for Administrators that select SSO authentication.

Activate provider ^

- SAML 2.0
- Custom OpenID Connect
- Google OpenID Connect
- Microsoft OpenID Connect
- Barracuda BCC Login
- Email backed

**User directories**

Add Directory v

List

Auto

### Google OpenID Connect

When choosing this option, there are no additional steps to configure. The identity provider is now configured.

### Microsoft OpenID Connect


When choosing this option, write a comma-separated list of all Microsoft Azure AD Tenant IDs you wish to use for SSO.

Each tenant ID will become a link once you accept the form. An Azure administrator must click on each of these links to grant administrator consent to our OpenID Connect Authenticator app.

## Custom OpenID Connect

Your provider will require the following fields:

- Client ID
- Client secret
- Metadata URL
- Email Claim



Settings

Users 505

Authentication

Identity providers

User directories

List

### Custom OpenId Connect

Information needed by your Identity Provider

SSO Redirect URL

<https://api.us.access.barracuda.com/sso/oidc>

Information provided by your Identity Provider

Client ID

39778ea6-a114-407e-94b9-a033f9fcdca1

Client secret

some\_password

Allowed Issuers

<https://idp.example/issuer1...>; <https://idp.example/issuer2...>

Email Claim

email; username; preferred\_username

Cancel Activate

Refer to your Identity Provider configuration manual for how to retrieve these configuration values.

## Figures

1. ActivateProvider.png
2. CustomIDConnectWindow.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.