

Validate Path

https://campus.barracuda.com/doc/96772167/

This section includes the following topics:

- Input Parameters
- Output Parameters

Input Parameters

The following table provides the parameters and descriptions.

Parameter	Description
diskLocation path	String disk path location.
	Optional, in case the path is a network share that requires auth. userName - optional parameter to use for shares requiring auth. password - optional parameter to use for shares requiring auth.

Example

Example for credential based auth on a remote host below. If a local folder is used, the credentials section is not required.

```
"diskLocation": {
    "path": "\\\server1\\share1\\folder1",
    "credentials": {
```

<u>Validate Path</u> 1 / 4

Barracuda Intronis Backup



```
"userName": "user1",

"password": "passwordtext"
}
```

Output Parameters

None when successful, validation errors otherwise:

CreateFolderFailed: general error. Most likely a local volume is read only or cannot be written to due to permissions on the local file system

Network shares only:

- BackupSetActions NetworkShareInaccessible network share address could not be reached
- BackupSetActions NetworkPathNotFound the network path could not be found
- BackupSetActions_NetworkShareInvalidAuth username + password combination failed authentication
- BackupSetActions_NetworkShareNoWritePermissions username and password ok, but no write permissions for the provided username on that share.

Example POST

POST /v2/accounts/test_acc/computers/0000/restore/diskimage/standard/vm/validate/path

<u>Validate Path</u> 2 / 4



Input Parameters

```
"diskLocation": {
    "path": "\\\server1\\share1\\folder1",
    "credentials": {
        "userName": "user1",
        "password": "passwordtext"
     }
}
```

Output Parameters

Response status: 204 No content (for online operation).

<u>Validate Path</u> 3 / 4

Barracuda Intronis Backup



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

<u>Validate Path</u> 4 / 4