

---

## How to Uninstall the Barracuda VPN Client for macOS

<https://campus.barracuda.com/doc/12468/>

To uninstall the Barracuda VPN Client for macOS and all of its components from a system, remove the Barracuda VPN Client executables using the command line. Make sure that your local user account has the required administrator rights to uninstall the Barracuda VPN Client.

### Before You Begin

---

Before uninstalling the Barracuda VPN Client, close the program and terminate any established VPN connections.

### Uninstall the Barracuda VPN Client version 5.1.7 and higher

---

1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
2. Open a command line window.
3. Remove the Barracuda VPN Client executables. At the command line, enter:
  - `rm -rf /Applications/Barracuda\ VPN\ Client.app`
  - `rm -rf /Users/[USERNAME]/Library/Group\ Containers/group.com.barracuda.Barracuda-VPN-Client`

You can also delete these executables with the Finder.

The Barracuda VPN Client and all of its components are now completely removed from the system.

### Uninstall the Barracuda VPN Client version 4.0 and higher

---

1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
2. Open a command line window.
3. Remove the Barracuda VPN Client executables. At the command line, enter:
  - `rm -rf /Applications/BarracudaVPNClient.app`
  - `rm -rf /Users/[USERNAME]/.barracudavpn`
4. (Optional) To remove kernel extensions (.kext) that have been deprecated since macOS 10.15.4, enter:
  - `rm -rf /Library/Extensions/tun.kext`
  - `rm -rf /Library/Extensions/tap.kext`

The Barracuda VPN Client and all of its components are now completely removed from the system.

---

## Uninstall the Barracuda VPN Client version 3.6.5 and higher

---

1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
2. Open a command line window.
3. Remove the Barracuda VPN Client executables. At the command line, enter:
  - `rm -rf /Applications/BarracudaVPNClient.app`
  - `rm /usr/local/bin/barracudavpn`
  - `rm /usr/local/bin/barracudavpn.engine`

You can also delete these executables with the Finder.
4. (Optional) To remove any certificates and licenses, enter:
  - `rm -rf /System/Library/barracudavpn/*`
  - `rm -rf /Library/barracudavpn/*`

The Barracuda VPN Client and all of its components are now completely removed from the system.

---

## Uninstall the Barracuda VPN Client below version 3.6.5

---

1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
2. Open a command line window.
3. Remove the Barracuda VPN Client executables. At the command line, enter:
  - `rm -rf /Applications/BarracudaVPNClient.app`
  - `rm /usr/sbin/barracudavpn`
  - `rm /usr/sbin/barracudavpn.engine`

You can also delete these executables with the Finder.
4. (Optional) To remove any certificates and licenses, enter:
  - `rm -rf /System/Library/barracudavpn`

The Barracuda VPN Client and all of its components are now completely removed from the system.

© Barracuda Networks Inc., 2026 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.