

# Deploying the Barracuda Web Security Gateway with a Peer Proxy

https://campus.barracuda.com/doc/32342219/

### **Proxying HTTP and HTTPS Traffic**

If you are running version 16.0 or higher of the Barracuda Web Security Gateway, you can enable sending both outbound HTTP and HTTPS traffic to a peer proxy either inside the network or in the cloud. If you are running an earlier version, you can only proxy HTTP traffic, not HTTPS. Configure on the **ADVANCED > Proxy** page in the Barracuda Web Security Gateway web interface.

### Deployment

In this deployment, the Barracuda Web Security Gateway is deployed inline or as a proxy and is configured to forward all port 80 (and, with version 16.0 and higher, HTTPS (443)) traffic to a preexisting proxy server. The proxy server can be anywhere on or off the network, and it sends filtered traffic from the Barracuda Web Security Gateway to the Internet. The Barracuda Web Security Gateway just needs to be configured with the IP address and port of the proxy server as described below. Note that with versions 15.x and lower, HTTPS(443) traffic will go straight out to the Internet after being filtered, even with SSL Inspection configured.

For this deployment, configure the following on the **ADVANCED** > **Proxy** page of the Barracuda Web Security Gateway web interface:

- 1. **Peer Proxy IP**: Enter the IP address of a pre-existing proxy server which will forward traffic from the Barracuda Web Security Gateway to the Internet.
- 2. **Peer Proxy Port**: If you have a pre-existing proxy server, enter the port number used for HTTP requests.

#### **Using SSL Inspection**

If you have this feature enabled on the Barracuda Web Security Gateway, to protect sensitive data, it is recommended to only use SSL Inspection if the peer proxy server is deployed inside the firewall. To use SSL Inspection, see <u>How to Configure SSL Inspection</u>.

#### **Using Authentication**

# Barracuda Web Security Gateway



Authentication is supported with a peer proxy if the Barracuda Web Security Gateway is deployed in a proxy configuration. See <u>Forward Proxy Deployment of the Barracuda Web Security Gateway</u>.

# Barracuda Web Security Gateway



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.