

How to Manage Multiple Systems with the Barracuda Cloud Control

<https://campus.barracuda.com/doc/3538958/>

Barracuda Cloud Control enables administrators to manage, monitor and configure multiple Barracuda Load Balancers (firmware version 3.6 and higher) at one time from one console. You can connect one or more Barracuda Load Balancers to Barracuda Cloud Control by doing the following:

1. If you don't already have an account with Barracuda Networks, visit <http://login.barracudanetworks.com> to create one.
2. Make a note of your username (email address) and password.
3. Log into your Barracuda Load Balancer as the administrator. On the **ADVANCED > Firmware Upgrade** page, check to make sure you have the latest firmware installed. If not, download and install it now.
4. From the **ADVANCED > Cloud Control** page, enter the Barracuda Networks username and password you created, and click **Yes** to connect to Barracuda Cloud Control. Note that your Barracuda Load Balancer can connect with only one Barracuda Cloud Control account at a time.
5. Log into Barracuda Cloud Control with your username and password. The Barracuda Load Balancer statistics display in the **BASIC > Status** page. To access the web interface of your Barracuda Load Balancer, click on the link in the Products column in the pane on the left side of the page, or you can click on the product name in the Product column of the Unit Health pane on the right side of the page.
6. Follow steps 3 and 4 to connect every subsequent Barracuda Load Balancer to Barracuda Cloud Control.

To disconnect your Barracuda Load Balancer and Barracuda Cloud Control, from the **ADVANCED > Cloud Control** page, enter the Barracuda Cloud Control username and password, and click **No** for **Connect to Barracuda Cloud Control**. Use this step when there is to be a loss of connectivity between the appliance and Barracuda Cloud Control due to the appliance being physically moved, or when there are other network connectivity issues.

Related Articles

- [Monitoring](#)
- [How to Configure SNMP Monitoring on the Barracuda Load Balancer](#)

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.