

## How to Determine the Current PST Enterprise Configuration

<https://campus.barracuda.com/doc/44434787/>

This article applies to the Barracuda PST Enterprise version 3.1 or higher.

When re-installing, upgrading, or migrating the PST Enterprise system, you must note your existing system configuration:

### Version 5.2 and Later

The current configuration is stored in the **System.ini** file in the Local Configuration Store (LCS) directory on the PST Enterprise server (**C:\ProgramData\Barracuda\PSTEnterprise\LocalConfigurationStore**).

Open the **System.ini** file in a text editor such as Notepad, and make a note of the following values:

- The PST Enterprise service account name (by default named **PSTEnterpriseAdmin**)
- The PST Enterprise Administrators security group (by default named **PSTEnterpriseUsers**)
- The SQL instance used to host the PST Enterprise database (by default **LOCALHOST\PSTEnterprise**)

### Version 5.1 and Earlier

The PST Enterprise Admin account name (by default named **PSTEnterpriseAdmin**):

1. This can be found in **C:\Program Files (x86)\Barracuda\PSTEnterprise\Web\web.config**.
2. Open this file in an editor such as Notepad, and find the line:

where **DOMAIN\PSTEnterpriseAdmin** is the Active Directory (AD) domain and PST Enterprise Admin account name.

The PST Enterprise Administrators security group (by default named **PSTEnterpriseUsers**):

1. This can be found in **C:\Program Files (x86)\Barracuda\PSTEnterprise\Web\web.config**.
2. Open this file in an editor such as Notepad, and find the line:

where **PSTEnterpriseUsers** is the security group name.

The SQL instance used to host the PST Enterprise database (by default

**LOCALHOST\PSTEnterprise):**

1. This can be found in **C:\Program Files (x86)\Barracuda\PSTEnterprise\Web\web.config**.
2. Open this file in an editor such as Notepad, and find the line:

where **SERVER\PSTENTERPRISE** is the SQL instance name.

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.