

Using the CudaLaunch VPN Connections for Native Apps

<https://campus.barracuda.com/doc/45028154/>

When using the CudaLaunch VPN connections to connect to the Barracuda NG Firewall, you can use native apps on your mobile device to access resources in the corporate network that are otherwise not accessible. For example, it is not possible to use RDP Application Tunneling resources directly in CudaLaunch, but you can use a local RDP app to connect to that same Terminal Server via the CudaLaunch VPN connection. The same applies for other mobile and desktop devices or corporate services requiring special client software. VPN Configuration for CudaLaunch done through SSL-VPN VPN Templates.



In this article:

Before you Begin

Configure the Barracuda NG Firewall for CudaLaunch. For more information, see [NG Firewall Configuration for CudaLaunch](#).

Step 1. Provision VPN Connections via VPN Templates in the SSL VPN Service

By adding group-policy-based VPN templates to your NG SSL VPN Resources, you can let end users connect to the Barracuda NG Firewall via VPN connection from their Android or iOS devices. The VPN Templates are automatically downloaded when starting CudaLaunch. CudaLaunch on Android uses our own TINA VPN client; CudaLaunch on iOS manages the built-in IPsec VPN client.


For more information, see [How to Configure VPN Templates in the SSL VPN](#).


Step 2. Establish the VPN Connection

You must trigger the VPN connection to allow the device to access the internal corporate resources.

CudaLaunch (Android and iOS)

In CudaLaunch, all available VPN connections are on the middle screen. Swipe left or right to the **VPN Connections** screen and tap on a VPN Template to establish a Client-to-Site VPN connection.






Connected to External beta - external IP

You can now access the corresponding
network throughout your device

Disconnect






Built-in IPsec VPN Client (iOS only)

After self-provisioning the IPsec VPN connection via CudaLaunch, you can also directly go to the built-in iOS VPN client to trigger the Client-to-Site connection, without having to log into CudaLaunch.

- On the home screen, go to **Settings** and tap **General**.
- Go to **VPN** and enable the VPN connection. A VPN icon will be displayed in the status bar.





Step 3. Use Local Apps via CudaLaunch VPN Connection

As soon as the VPN connection is established, the user can access corporate information by launching the locally installed apps.

Depending on which resource you connect to, choose an appropriate app from your platform's app store.

Example 1 - Use Remote Desktop App on an iOS Device to Connect to a Terminal Server

To use Remote Desktop Client on an iOS or Android device, start CudaLaunch and connect to the VPN. Launch the native Remote Desktop app and enter the IP address of the terminal server. The traffic is now routed through the VPN tunnel of the Barracuda NG Firewall.

Example 2 - Use an SSH Client App on an iOS Device

To use an SSH client on your iOS or Android device, start CudaLaunch and connect to the VPN. Launch the native SSH app and enter the IP address and the user credentials for the remote server. The traffic is now routed through the VPN tunnel of the Barracuda NG Firewall.

Figures

1. UsingLocalApps.png
2. CudaLaunch03.png
3. CudaLaunch05.png
4. CudaLaunch06.png
5. iOS1.png
6. iOS2.png

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.