

How to Uninstall the Barracuda VPN Client for macOS

https://campus.barracuda.com/doc/46206595/

To uninstall the Barracuda VPN Client for macOS and all of its components from a system, remove the Barracuda VPN Client executables using the command line. Make sure that your local user account has the required administrator rights to uninstall the Barracuda VPN Client.

Before You Begin

Before uninstalling the Barracuda VPN Client, close the program and terminate any established VPN connections.

Uninstall the Barracuda VPN Client version 4.0 and higher

- 1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
- 2. Open a command line window.
- 3. Remove the Barracuda VPN Client executables. At the command line, enter:
 - rm -rf /Applications/BarracudaVPNClient.app
 - ∘ rm -rf /Users/[USERNAME]/.barracudavpn

You can also delete these executables with the Finder.

- 4. (Optional) To remove any certificates and licenses, enter:
 - ∘ rm -rf /Library/Extensions/tun.kext
 - ∘ rm -rf /Library/Extensions/tap.kext
- 5. The Barracuda VPN Client and all of its components are now completely removed from the system.

Uninstall the Barracuda VPN Client version 3.6.5 and higher

- If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
- 2. Open a command line window.
- 3. Remove the Barracuda VPN Client executables. At the command line, enter:
 - ∘ rm -rf /Applications/BarracudaVPNClient.app
 - rm /usr/local/bin/barracudavpn
 - rm /usr/local/bin/barracudavpn.engine

You can also delete these executables with the Finder.

- 4. (Optional) To remove any certificates and licenses, enter:
 - o rm -rf /System/Library/barracudavpn/*
 - ∘ rm -rf /Library/barracudavpn/*



The Barracuda VPN Client and all of its components are now completely removed from the system.

Uninstall the Barracuda VPN Client below version 3.6.5

- 1. If a Barracuda VPN Client shortcut was created in the Dock, remove the shortcut.
- 2. Open a command line window.
- 3. Remove the Barracuda VPN Client executables. At the command line, enter:
 - ∘ rm -rf /Applications/BarracudaVPNClient.app
 - ∘ rm /usr/sbin/barracudavpn
 - rm /usr/sbin/barracudavpn.engine
 You can also delete these executables with the Finder.
- 4. (Optional) To remove any certificates and licenses, enter:
 - ∘ rm -rf /System/Library/barracudavpn

Barracuda Network Access Client



© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.