

How to Install the Barracuda Network Access/VPN Client for Windows

<https://campus.barracuda.com/doc/46206821/>

Install the Barracuda Network Access Client for Windows. This setup contains the Barracuda VPN Client, the Barracuda Personal Firewall, and the Barracuda Health Agent. Installation requires local administrator rights.


Do not run the installation executable from a network share. Instead, copy the installation files to a local hard drive and run it from there. Otherwise, the installation will fail because all network connections are terminated for a few moments during the installation process.

Requirements

- **License** - (depending on authentication type):
 - Barracuda personal license
 - X.509 certificate

Before You Begin

Download the 32- or 64-bit Network Access/VPN Client for Windows from the [Barracuda Download Portal](#).

 **Barracuda** | Barracuda NG Download Portal Log Out

Type

Firmware

Hotfix

NAC / VPN Client

NextGen Admin

Network Access Client


Search

Name	Summary	Type	Date	Size
Barracuda Network Access Client 4.0 64-bit (EXE)	Bundled VPN Client and Network Access Client for 64-bit Microsoft Windows	NAC / VPN Client	Aug 2, 2016	39.4 MB
Barracuda Network Access Client 4.0 32-bit - Hotfix 101	Hotfix 101 - Barracuda Network Access Client 4.0 32-bit	NAC / VPN Client	Sep 8, 2016	3.2 MB


Install the Barracuda Network Access Client

Install the Barracuda Network Access Client on a dedicated Windows workstation.


1. Double-click the *setup.exe* file for the Barracuda Network Access Client. The InstallShield Wizard then starts to prepare the installation files.



2. After the installation files are prepared, the InstallShield Wizard starts the setup process. When a pop-up window opens and advises you to close all running programs, close the programs.
3. Click **Next** to continue.
4. Accept the **License Agreement**, and click **Next**.
5. Enter your **User Name** and **Organization**. You can also choose to install the Barracuda Network Access Client for either **Anyone who uses this computer (all users)** or **Only for me**.




6. Click **Next** to continue.
7. Chose to install the Barracuda Network Access Client at the default location, or click **Change** and select another target directory.
8. Click **Next**.
9. Select **Barracuda VPN and NAC Client** to initiate a complete installation.



10. Click **Next**.

11. Configure the basic settings (you can also configure these settings later):


- **VPN Server IP(s)** – Enter one or more IP addresses for VPN servers. These will be used in the default VPN profile. Separate multiple entries with a semicolon (;).
- **Network Access Control IP** – If applicable, enter the IP address of the Access Control Service.
- **Terminate Password** – The master password that must be entered in the Barracuda Network Access Client by users before they can terminate the client or modify advanced settings. This is to prevent users from simply shutting down the client or modifying certain settings in order to bypass its security functions. Leave the field empty to disable the master password. The password set here can be changed later only via the Access Control Service in Barracuda Firewall Admin by navigating to **Access Control Service Trustzone > Settings > Client Shutdown Passphrase**.



12. Click **Next**, and install the Barracuda Network Access Client.



13. Wait until the progress bar reaches 100%, indicating that the installation is complete. During this subprocess, the system's network connectivity will drop out for a few moments. When a pop-up window opens and advises you to restart your computer, click **Yes**.
14. The wizard tells you when the installation has been completed.
15. To start the VPN Client when you click **Finish**, select the **Launch VPN Client** check box.



You can now connect and configure the settings. Continue with [Getting Started](#).

Figures

1. nac_vpn_install_dl.png
2. nac_vpn_install_00.png
3. nac_vpn_install_02.png
4. nac_vpn_install_03.png
5. nac_vpn_install_04.png
6. nac_vpn_install_05.png
7. nac_vpn_install_06.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.