
How to Change Control Center Credentials for Non-Root Admins

<https://campus.barracuda.com/doc/46893865/>


In the Barracuda NG Admin settings, you can configure the password and key for non-root admins of an NG Control Center.

In this article:

Change Password for Non-Root Admins

Change the password used to authenticate when connecting to an NG Control Center

1. In the top left of NG Admin, click **OPTIONS** and select **Settings**.
2. Expand **Admin and CC Settings**.
3. Click the list below the **Admin and CC Settings** and select **Change Admin Credentials for CC Admin**.
4. In the **CC Selection** section, select the Control Center from the **CC** drop-down list.
5. Select the Control Center IP address from the **Address** drop-down list.
6. In the **Change Administrator Password** section, enter:
 - **Login Name**
 - **Old Password**
 - **New Password** and **Confirm**



7. Click **Change Password**.

Change Administrator Key for Non-Root Admins

Change the client certificate used to authenticate when connecting to an NG Control Center.

1. In the top left of NG Admin, click **OPTIONS** and select **Settings**.
2. Expand **Admin and CC Settings**.
3. Click the list below the **Admin and CC Settings** and select **Change Admin Credentials for CC Admin**.
4. In the **CC Selection** section, select the Control Center from the **CC** drop-down list.
5. Select the Control Center IP address from the **Address** drop-down list.
6. In the **Change Administrator Key** section, enter the **Login Name** and **Password**.
7. Click **Import Public** and upload the new certificate.

Admin and CC Settings

Legacy Configuration

Show legacy configuration elements

Change Admin Credentials for CC Admin

CC Selection

CC	ngcc-00130000001pRGt	Remove Entry	
Address	10.0.10.77	Remove Entry	Show Certificate...

Change Administrator Password (for non-root users)

Login Name	<input type="text"/>	Old Password	<input type="text"/>	
New Password	<input type="text"/>	Confirm	<input type="text"/>	Change Password

Change Administrator Key

Login Name	youradminuser	Password	●●●●●●●●	
Imported Key	- None -	Import Public	Clear	Change Admin Key

8. Click **Change Admin Key**.

Figures

1. CC_Admin_password_01.png
2. CC_Admin_password_02.png

© Barracuda Networks Inc., 2020 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.