


Licenses Page

<https://campus.barracuda.com/doc/53248631/>

The **Licenses** page lets you view the license status of your Barracuda NextGen Firewall F-Series. To access the **Licenses** page, open the **CONTROL** tab and click the **Licenses** icon in the ribbon bar.



ACTIVE LICENSES

In the **Active Licenses** table, all active licenses are listed.

ACTIVE LICENSES

Name/Module	License	Expires	HostID	Status
base-bnvf2000	TKA2321094-VF-2000-Pool-18-05-2019-18-00-00	02.01.2030 01:00:00	float-v1	Float-Confirmed-for-12days
add-bnvf2000-vp	TKA2321094-VF-2000-Pool-18-05-2019-18-00-00	19.05.2019 19:00:00	float-v1	Float-Confirmed-for-12days
add-bnvf2000-a	TKA2321094-VF-2000-Pool-18-05-2019-18-00-00	19.05.2019 19:00:00	float-v1	Float-Confirmed-for-12days
add-bnvf2000-e	TKA2321094-VF-2000-Pool-18-05-2019-18-00-00	19.05.2019 19:00:00	float-v1	Float-Confirmed-for-12days
URL-Filter				
energize				
App-Detection				
ips				
add-bnvf2000-w	TKA2321094-VF-2000-Pool-18-05-2019-18-00-00	19.05.2019 19:00:00	float-v1	Float-Confirmed-for-12days

Information on each module is organized in the following columns:

- **Name/Module** - The module name.
- **License** - The license number.
- **Expires** - The license expiration date and time.
- **Host ID** - The hardware ID the license is attached to.
- **Status** - The status of the license.

To open the license configuration, double-click it. For more information, see [Licensing](#).

To see what services are covered by the license, click the **+** icon to the left of the green check mark. This expands the license entry and shows details on the license module.

License Values

The **License Values** section displays details for your license, such as your product model, appliance type, serial number, and number of licensed tunnels.

```
License Values
License: Barracuda
License-Virtual: True
License-Model: VF2000
SSLVPNAC: licensed
Demo Mode: no
Export Mode: no
CC managed: yes
Platform:
Product: vf2000
Configured Appliance: VF2000
Detected Appliance: VM
Serial Number:
Flash based: no
Statistics: yes
Licensed Tunnels: unlimited
Compression: licensed
Hardware Encryption: not-licensed
```

VERSION STATUS

In the **Version Status** table, you can view the version, build date, and status of the installed Barracuda Networks software modules.

VERSION STATUS

Module	Type	Version	Status	Comment
✓ acpf	kernel-module	phionnet_acpf-7.1.0-122.x86_64		7.1.0.120
✓ ktina	kernel-module	phionnet_ktina-7.1.0-138.x86_64		6.0.0.5
✓ URL-Filter	server	phionnet_cofsd-7.1.0-55.i386	Float-Confirmed-for-12days	-
✓ DHCP-Relay	server	phionnet_dhcp_relay-7.1.0-51.i386	Float-Confirmed-for-12days	-

Information on each module is organized in the following columns:

- **Module** – The module name.
- **Type** – The type of module.
- **Version** – The version of the module.
- **Status** – The status of the module, which can be any of the following:
 - Latest Kernel – The latest NGFW OS-compiled kernel.
 - Clean Release – Release version number/binary match.

- Dirty Release – Release version number/binary mismatch.
- No License Found – No license found for this module.
- Not Used – This module is not used.
- **Comment** – Any additional comments.


To view more detailed information about an entry, double-click it.

Selecting Categories for Display in the Version Status Table

You can customize the categories of the columns shown in the **VERSION STATUS** table.

To customize the categories:

1. Right-click inside of the display area of the **VERSION STATUS** table.
2. In the pop-up menu, click on **Select Columns...**
3. From the **Available Columns** table, select the category that you want to be displayed in the table.
4. Click on the > button to move the information field from the column **Available Columns** to the **Current Columns**. Entries in the table **Current Columns** will be displayed in the list order. Click on < to remove the category from the values to be displayed.
5. To the apply changes, click **Close**.




Reordering Columns in the VERSION STATUS Table

To reorder the columns in the process table, drag and drop the column header to your desired position.

HOST IDs

The **Host IDs** section lists the hardware IDs that the node-locked licenses can be attached to.



Figures

1. licenses_page_00.png
2. active_licenses_00.png
3. license_values_00.png
4. version_status_00.png
5. version_status_01.png
6. host_ids_00.png

© Barracuda Networks Inc., 2021 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.