












EVENTS Tab

<https://campus.barracuda.com/doc/53248836/>

The Barracuda NextGen Admin **EVENTS** page lets you monitor and manage events generated by the Barracuda NextGen Control Center and F-Series Firewalls. To access the **EVENTS** page, click the **EVENTS** tab in the ribbon bar. For information how to configure eventing, see [Events](#).

DASHBOARD CONFIGURATION CONTROL FIREWALL NAC VPN MAILGW DHCP PROXY WI-FI LOGS STATISTICS **EVENTS** SSH 






 Filter  No Auto Refresh  Refresh (F5)  Disconnect

Current Event							
1 Network							
1 boxnet							
2232 Logical Network Subsystem Configuration							
Time: 2016.01.12/13:34:54 / Count: 32							
Event Time	Event	Desc	Count	Layer desc	Class desc	Type	
 2016.01.28/08:49:05	NG Firewall Login Notice	root	481	boxconfig	Login	2420	
 2016.01.28/08:47:43	NG Firewall Login Notice	root	167	event	Login	2420	
 2016.01.28/08:47:30	NG Firewall Login Notice	root	2921	control	Login	2420	
 2016.01.28/08:47:21	NG Firewall Login Notice	root	310	phiona	Login	2420	
 2016.01.28/08:44:29	Start Service	S1_DHCP	36406	control	controld	2001	
 2016.01.28/02:35:24	Release Inconsistencies Detected	rpm verific...	398	release mainte...	phionRelCheck	4410	

The events table displays events information in the following columns:

- **Event** - The name of the event.
- **Event Time** - The date and time the event was generated.
- **Desc** - The event description.
- **Count** - The number of times the event occurred.
- **From Box** - (CC only) The name of the system that created the event.
- **Layer desc** - The layer that the event occurs on.
- **Class desc** - The class that the event belongs to.
- **Type** - The event type.

On the **Events** page, the importance and type of each event is determined by its icon and the font that it is displayed in:

Icon	Event Type
	Information
	Warning
	Error
	Notice
	Security

Text Type	Event Type
normal text (blue)	New and unread event.
normal text (black)	Uncritical or confirmed event.

bold text (black)	Indicates that changes were made to default configuration of the event. For more information, see How to Configure Basic, Severity, and Notification Settings for Events .
--------------------------	--

Acknowledging Events and Alarms

Some events, such as error events or events that are displayed in blue text, require acknowledgement. You can also determine if an event needs acknowledgment by double-clicking it to view its properties. When you acknowledge an event, it is then displayed in black normal or bold text. If an event has an alarm, you can also either reset or disable the alarm.

If an event must be confirmed and is in alarm condition, deleting the alarm will also delete the request for acknowledgement. If an alarm is stopped, any configured repeating server actions are also stopped.

To acknowledge an event that requires confirmation, right-click the event and select **Send - Acknowledgement**. Acknowledging the event also terminates any alarms (such as a sound playing or an email notification) that have been set for it.

- To acknowledge an event and remove a warning icon from it, select **Send - Reset Alarm**.
- To mark an uncritical event as read, select **Send - Mark as Read**.
- To temporarily disable the event alarm, select **Temporary Disable**. The event is then displayed in italics.


Managing Events

To manage the list of events that are displayed, you can refresh the list automatically or manually, delete events, and specify which columns are displayed or hidden. To delete an event, right-click it and select **Delete Event**. To verify that an event has been properly deleted, refresh the event list. To automatically refresh the list of events in **Live** mode, click **No Auto Refresh** and then click **Live**.

Notification messages are only enabled in **Live** mode. This mode displays of the current event system status and enables pop-up windows and sound. To manually refresh the list of events, click **Refresh**. To hide and show columns, right-click the list of events and select **Columns**. In the **Show / Hide Event Columns** window, select the columns that you want to be displayed.

Filter Options

To filter the list of events that are displayed, click the **Filter** icon on the top right of the page. To enter values for a filter setting, click the setting button. For example, to enter a layer ID, click **Layer ID**. In the **Add Criterion** window, add the values to the setting list and then click **Add**. After adding all of the required values for the filter, click **Activate**.



Filter

Time

from 10:40:16 / 18:05:2012

to 10:40:16 / 18:05:2012

Enabled: on off both

Alarm: on off both

Confirm: yes no both

Priority: low medium high*

** Events with priority 100 are always displayed.*

Layer ID 2

Desc

Class ID 3

Desc

Type ID 11

Desc

Message

from Box

Activate Disable Cancel

Viewing Event Properties

To view detailed information for an event, you can either double-click it or right-click it and select **Properties**. From the **Page 1** tab, you can view the system, layer, class, and type for the event, as well as its event ID.

Field	Description
-------	-------------

Box	The IP address of the system that created the event.
Layer	There are three layers: <ul style="list-style-type: none"> • 1—Boot layer. • 2—Box layer. • 3—Server/Service layer.
Class	There are three classes: <ul style="list-style-type: none"> • 1—Operative • 2—Resources • 3—Security
Type	The event ID.

From the **Page 2** tab, you can view the dates and times of when the event was confirmed, acknowledged, or had its alarm disabled. You can also view information about the administrator who confirmed the event.

- **by Admin** - The administrator who confirmed the event. If the event is unconfirmed, this field is empty.
- **by Peer** - The IP address for the workstation of the administrator who confirmed the event. If the event is unconfirmed, this field is empty.
- **Date** - The date and time of when the event was read or confirmed. If the event is unconfirmed, this field is empty.
- **Insert** - The date and time of when the event was generated.
- **Box** - Internal system information related to the insert time (please ignore this value).
- **Update** - The date and time of any status changes for the event, such as when it was acknowledged or marked as read.
- **Alarm** - The date and time of when the alarm was sent.
- **t. disabled** - The date and time of when the alarm was disabled temporarily.

Figures

1. events.png
2. information.png
3. warning.png
4. error.png
5. notice.png
6. security.png
7. event_filter.jpg

© Barracuda Networks Inc., 2019 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.