

How to Configure SAML 2.0 Configuration

https://campus.barracuda.com/doc/93201535/

Security Assertion Markup Language (SAML) is a standard protocol that gives identity providers (IdP) such as CloudGen Access a secure way to let users access a service provider such as Jira Cloud, Slack, and others. SAML authentication can be configured for enrolling devices through a specific identity provider.

Configure SAML

To configure SAML:

- 1. Go to **Identity > Settings**.
- 2. In the Authentication Protocol section, click Activate Provider.
- 3. Click on **SAML 2.0**.

Authentication protocol		
Identity provider	This setting enables enforcement of authentication for all users when enrolling a new device and for Administrators that select SSO authentication.	
	Activate provider	
	SAML 2.0	
	Custom OpenID Connect	
	Google OpenID Connect	
User directories	Microsoft OpenID Connect	ត្តក្តិត្តំ Add Directory 🗸
	Barracuda BCC Login	
List	Email backed	Auto

- 4. Your provider will require the following fields:
 - Identifier (Entity ID)
 - Assertion Consumer Service URL
 - SSO URL



		enterprise.fyde.com	Ċ		۵
<	Settings				
		Service Provider Information			
Overview	General	Use this information for your Identity Provider			
A Identity	Identity Provi Configuration	Identifier (EntityID) https://enterprise.fyde.com/sp/metadata	P	l users when enrolling a new device	
Access	SAML	Assertion Consumer Service URL https://enterprise.fyde.com/sp/acs	P		
DNS Security		sso url https://enterprise.fyde.com/sp/SSO	P		
Activity	Agent Custor	Information retrieved by the Identity Provider			
ⓒ} Settings	App Configur	Identifier (Entity ID) *		creen inaccessible.	
		Redirect URL (SSO URL) *			
		Certificate *			
		Cancel	Ok	ble. Only available on iOS.	
0			_		(

- 5. Follow one of the provider-specific steps below to obtain the required fields:
 - \circ Entity ID
 - Redirect URL (SSO URL)
 - \circ Certificate

Provider-Specific Steps

- How to Configure Microsoft Entra ID Authentication
- How to Confgure Okta For Authentication

Barracuda CloudGen Access



Figures

- 1. ActivateProvider.png
- 2. ec-saml-enterprise-console-settings-menu.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.