

How to Activate and License a Stand-Alone Virtual or Public Cloud Firewall or Control Center

https://campus.barracuda.com/doc/98210668/

You must enter the license token received from Barracuda Customer Services after you purchase your virtual firewall license. Barracuda Firewall Admin transmits the token to the Barracuda Licensing service and initiates the activation process. After completing the customer information form and accepting the EULA, your license is activated and automatically downloaded and installed on your unit.

Before You Begin

- Locate the license token in the email you received from Barracuda Networks Customer Services after purchasing your CloudGen Firewall Vx, AWS, Google Cloud, or Azure license.
- Barracuda Firewall Admin must be able to connect to the Barracuda licensing servers.
- If you are licensing a CloudGen Firewall, the firewall must be able to connect to the Barracuda licensing servers. Barracuda Firewall Control Centers do not need to be able to access the Internet because the licenses are downloaded and installed via Barracuda Firewall Admin.
- (optional) Barracuda Firewall Admin automatically uses the proxy address in the Windows registry. If a proxy is entered but disabled, Barracuda Firewall Admin still uses it. You can enter a proxy in Barracuda Firewall Admin by navigating to OPTIONS > Settings > Barracuda Activation > Proxy Settings.

Step 1. Enter the License Token

- 1. Use Barracuda Firewall Admin to log into the firewall.
 - If the password has not been set during deployment, use the default credentials to log in:
 - Default User root
 - Default Password ngf1r3wall

The default password is intended for initial access only. You must change the password once you are logged into the CloudGen Firewall. For more information, see <u>How to Change</u> the Root Password and Management ACL.

- 2. Click the **DASHBOARD** tab, the **General** sub-tab, and locate the **Subscription Status** element.
- 3. Click the arrow icon next to the **Activation State** entry and select **Enter license token and activate the appliance**. The **Activate your Appliance** window opens.





4. Enter the license token.



- 5. Click **OK**. The product activation window opens.
- 6. Fill out the activation form.

In order to complete activa	tion of your product, please fill out the form below and p	ress the "Activate" button.	
Serial Number: BAR-	-		Is Eval License
Customer Information		Purchase Information	
First Name	100.00	Purchased From	Barracuda Networks
Last Name	10000	Salesperson Name	Barracuda Networks
Company Name	Barracuda Networks Techlib	Email	documentation@barracuda.com
Email		Phone	+43 508 100
Phone	100.000 00.000	Country	AUSTRIA
Country	AUSTRIA	City	Innsbruck
Street Address	Eduard Bodem Gasse 1	State/Province	Tirol
City	Innsbruck	Zip/Postal Code	6020
State/Province	Tirol		
Zip/Postal Code	6020		
Accept the Agreement			
General			
These terms are governed federal courts located in S representations that the C prohibited. If you choose 1 If any provision of these to pages of this site. Revised: December 2012	by the laws of the State of California, without respect anta Clara County, California, U.S.A., and both parties orbents is appropriate or available for use in any manner to access this site from outside the United States, you d erms is unenforceable, the other terms will remain in full	to its conflict of law principles. Any actus waive any objection to personal jurisdic and in particular outside the United Sta s so at your own initiative and you are r force and effect. Certain provisions of	in in connection with this site will be brought only in state or tion of and venue in such courts. Barracuda Networks makes no tes; and access from territories where the Content is illegal is responsible for complying with all local laws. these terms may be superceded or extended by terms on specific

- 7. (Optional) Choose the option Save your customer data for later activations.
- 8. Click **Activate**. After the activation process successfully completes, you will receive a notification email from Barracuda Networks.
- 9. The firewall automatically downloads and installs the purchased licenses. The license state on the **Dashboard > General** page changes to **OK**.

✓ SUBSCRIPTION STATUS		\$
License State	📀 OK (expires 31.12.2029)	€
Activation State	Query Barracuda Online for new Licenses	Э

Step 2. Check the License Status



Go to the **CONTROL** > **Licenses** page and verify that all of your purchased licenses are listed in the **Active Licenses** table.

Normal box operation	1						
ACTIVE LICENSES					Enter new License Token	Edit Licenses	License Values
Name/Module	License	Expires	HostID	Status			License: Barracuda
vpnac		- 01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID		^	License-Virtual: True License-Model: VF500
🛓 🥑 base-bnvf500	-	- 01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID			Capacity: 500
							SSLVPNNAC: licensed
							Demo Mode: no
							CC managed: no
							Platform: Product: vf1000
							Configured Appliance: VF1000
DNS-Service							Detected Appliance: VM Setal Number: 904646
							Flash based: no
							Statistics: yes
Mail-Gateway							Compression: licensed
OSPF-RIP-BGP-Service							Hardware Encryption: not-licensed
Access-Control-Service							VPN Shaping: licensed
HTTP-Proxy							NAC: unlimited Protected IPs: unlimited
SNMP-Service							
SPAM-Filter							
VPN-Service							
add-bnvf500-a	-BN-VF500-AdvancedThreatDetection-	01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID			
add-bnvf500-e	-BN-VF500-Energize Update-	01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID			
add-bnvf500-m	-BN-VF500-MalwareProtection-	01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID			
add-bnvf500-v	-BN-VF500-RA-BASIC-	01.01.2030 01:00:00	CPU-0010-0F91-0000-00	Valid-Host-ID			
add-bnvf500-v	-RN-VE500-RA-PREMILIM-	01 01 2030 01:00:00	CPU-0010-0E91-0000-00	Valid-Host-ID		~	< >

Barracuda CloudGen Firewall



Figures

- 1. lic1.png
- 2. lic2.png
- 3. activation_form.png
- 4. lic_succ1.png
- 5. License-overview.png

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.