
How to Configure Automated Backups

<https://campus.barracuda.com/doc/39813220/> It is recommended to always have working backups of your appliance. In case of a hardware failure or system misconfiguration the backup files can be used to quickly restore the appliance to working order. The administrator can configure how many backups are saved to a SMB share, FTP or FTPS server.

Configure automatic backups

1. Log into the [Administrative web interface](#).
2. Open the **BASIC > Backups** page.
3. In the **Automated Backups** section, complete the following tasks:
 - Configure the remote server where the backups are stored. You can choose between SMB and FTP servers. You can verify the connection to the remote storage by clicking **Test Backup Server**.
 - Select the type of backups you want to create and set the time.
4. Click **Save Changes**.

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.