

How to Manually Update AOneDA from Version 3.0 to Version 3.1

<https://campus.barracuda.com/doc/66683346/>

This article applies to Barracuda ArchiveOne version 7.3.

The ArchiveOne Deployment Analyzer (AOneDA) provides the System Health functionality once ArchiveOne is installed. In order to update from ArchiveOne Deployment Analyzer version 3.0 to version 3.1, you must manually uninstall the existing version and install the new version. Once completed, no further manual updates are required.

To update AOneDA from version 3.0 to 3.1,

1. Log on to the Archive server as an administrative user.
2. From the **Control Panel**, open **Programs and Features**, and uninstall **AOneDA**.
3. Once uninstalled, download the [AOneDA version 3.1 MSI file](#).
4. Once the download is complete, double-click the file **AOneDASetup_3_1_0_4691.msi** to start the installer.
5. Click **Next** to proceed with the install.
6. Review and accept the **Licence Agreement**, and click **Next** to proceed.
7. Enter the **User Name** and **Organization** details (if desired), and click **Next** to proceed.
8. Click **Next** on the **Destination folder** page. *Do not change the default installation directory; it must be C:\Program Files (x86)\Barracuda\AOneDA.*
9. Click **Install** to start the installation process.
10. Once complete, click **Finish** to close the installer.

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.