


Editing Physical Imaging Standard Backup Sets

<https://campus.barracuda.com/doc/93197694/>

To edit a Physical Imaging Standard backup, perform the following steps. See [Navigating to the Computer Page](#) for instructions.

1. Navigate to the **Computer** page.
The **Computer** page is displayed.



Home > Manage > Barracuda > Physical (0001) Leave Feedback

Computer: Physical (0001)
View Computer (Barracuda) Support


Computer Information Edit

Backup agent: Connected
Computer name: Physical
Computer ID: 0001
Account username:
Email address:
Phone number: 1111111111
Group: Default Group
Local backup subscription: Enabled

Graph: 04/14/2017 - 07/14/2017
Y-axis: 0.0 B to 5.0 KB
X-axis: 6/2/2017, 6/16/2017, 7/7/2017

Active Recoveries (0) Activity System Software Notifications Backup Delete Restore


2. Click the **Backup** tab.
The **Backup Selections** page is displayed.




Backup Selections Export Backup Selection

Backup Type	Type	Backup Set	Run	Next Backup	Scheduled	Remove
Files and Folders (1)		Files and Folders 1		11/15/2017 @ 11:00 PM	<input checked="" type="checkbox"/>	
Physical Imaging Rapid Recovery		Hyper-V Standard 1		11/15/2017 @ 11:00 PM	<input checked="" type="checkbox"/>	
Physical Imaging Standard		Hyper-V Rapid Recovery		--	<input type="checkbox"/>	
Hyper-V Standard (1)		Hyper-V Rapid Recovery 1		Recurring	<input checked="" type="checkbox"/>	
Hyper-V Rapid Recovery (2)						
VMware Standard						
VMware QuickSpin						
SQL Server						
Exchange Information Store						
Exchange Mailbox Level						
System State						

1 - 4 of 4 items

3. Click the edit  icon to edit the backup selection.
The **Backup Set Summary** page is displayed.




Edit Backup

Physical Imaging Standard 1

Select Schedule Retention Advanced **Summary**

Select This backup set contains 2 volume(s), currently totaling 11.92 GB with a capacity of 40 GB

- System Reserved (System, Primary Partition)
- (C:) (Boot, Primary Partition)

Destination  Online

Schedule **Schedule 1** Every day @ 11:00 PM and are allowed to finish before starting the next schedule occurrence.

Retention Keep at least 28 day(s) and no fewer than 4 version(s).

Advanced A full backup is forced following every 21 incremental backup(s).
Take Copy-Mode Backups

< Previous

Cancel Update Backup Set

4. Select any of the tabs to display and edit your current settings. See [Creating Physical Imaging Standard Backups Sets](#) for details.
- The backup set name can be edited on any page.
5. After making all your edits, click the **Update Backup Set** button at the bottom of any page, as shown below.



Cancel Update Backup Set

The **Backup Selections** page is displayed with your current backup status.

Figures

1. edit.png
2. edit1.png
3. image046.png
4. edit2.png
5. image051.jpg

© Barracuda Networks Inc., 2024 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.