

How to Deploy Firewall Insights OVA on VMware

https://campus.barracuda.com/doc/13922/

To ease deployment, Firewall Insights devices are available as pre-built OVA images that can be imported into your VMware Hypervisor. You do not need to create or configure a virtual machine. Before deploying the Firewall Insights device, verify that the host system meets the minimum storage requirements, and review the resource recommendations for the production system. You can deploy the firewall using either the VMware vSphere Client or the VMware OVF Tool (ovftool).

Before You Begin

- For information regarding the sizing of your CPU, disk, and RAM, see <u>Deployment</u>.
- Before you start Firewall Insights for the first time, disconnect the network interface card.
- Download the VMware OVA image from the Barracuda Download Portal.

Before deploying Barracuda Firewall Insights on VMware ESX(i), make sure that your hypervisor meets at least the minimum system requirements shown below.

• **Minimum System Requirements** – VMware ESX(i) version 5.5.0 + all available updates or higher.

If you are using Google Chrome and encounter timeout or checksum issues while downloading the image, try Mozilla Firefox instead.

Use the VMware vSphere Client

- 1. Download the OVA image for your Firewall Insights from the Barracuda Download Portal.
- 2. Connect to your VMware Hypervisor using the vSphere Client.
- 3. Click File > Deploy OVF Template.

1 🕑	0.0.66.208 - vSphere Client		
File	Edit View Inventory Adr	minis	tration Plug-ins Help
	New	•	ntory 🕨 🛐 Inventory
	Deploy OVF Template		
	Export	×	
	Report	•	Information Development
	Browse VA Marketplace		Getting Started Summary Virtual Ma
	Print Maps	÷	What is a Descures Deal?
	Exit		what is a Resource Pool?



- 4. In the deployment wizard, click **Browse** and select the OVA image. Click **Next** to proceed.
- 5. Enter a name for the virtual machine to be created. Click **Next** to proceed.
- 6. Select the resource pool where Firewall Insights will be created. Click **Next** to proceed.
- 7. Select the data store that the Firewall Insights device should be installed on. When you import an OVA file with VMware 4.1 or later, you are offered the **Thin provisioned format** setting that lets you change the VM size. If you choose to reduce the VM size, do not choose a value below 2 TB. Barracuda Networks recommends that you select **Thick provisioned format**.

Deploy OVF Template Disk Format In which format do you	want to store the virtual disks?
Source OVF Template Details Name and Location Datastore Disk Format Network Mapping Ready to Complete	Information about the selected datastore: Name: speicher 1 Capacity: 1,7 TB Free space: 583,9 GB Select a format in which to store the virtual machines virtual disks: Thin provisioned format The storage is allocated on demand as data is written to the virtual disks. This is supported only on VMFS3 and newer datastores. Other types of datastores might create thick disks. Estimated disk usage: 1,9 GB for Thick provisioned format All storage is allocated immediately. Estimated disk usage: 80,0 GB
Help	< Back Next > Cancel

8. Map to the required network in your existing inventory and then click **Next** to proceed.



Network Mapping						
What networks should the	e deployed template use?					
	-					
Source OVE Template Details	Map the networks used in this OVF template to networks in your inventory					
Name and Location						
Datastore	Source Networks	DestinationNetworks				
<u>Disk Format</u>	VMwareImages	Management				
Network Mapping						
Ready to complete						
	Description:					
	Description:					
	Description: The VMwareImages network		-			
	Description: The VMwareImages network					
	Description: The VMwareImages network		-			
	Description: The VMwareImages network		-			
	Description: The VMwareImages network		-			
	Description: The VMwareImages network		-			
	Description: The VMwareImages network					
4 <u> </u>	Description: The VMwareImages network					

- 9. After the deployment wizard summarizes all your settings, click **Finish** to start the deployment process. After successful deployment, the Firewall Insights device is displayed in your VMware Hypervisor inventory list.
- 10. Select the Firewall Insights device from the list on the left and click **Edit Settings** to disconnect the network interface card before you boot for the first time.
- 11. Select the Firewall Insights device from the list on the left and click **Edit Settings** to edit settings such as **Disk Provisioning** with appropriate values. See <u>Deployment</u>.
- 12. Continue with Next Step below.

Use the VMware OVF Tool

- Download the VMware OVF Tool from <u>vmware.com</u>. Use the following command: ovftool -datastore=datastorename ovaimage vi://server-ip Note the following:
 - \circ datastore $\,$ The name for the data store.
 - ovaimage The path and name of the OVA file.
 - server-ip The IP address for the virtual appliance.
- 2. Configure the resources pool and the network mapping within the VMware virtual machine settings.
- 3. Continue with Next Step below.

Next Step

Barracuda Firewall Insights



After deploying the Firewall Insights device, continue with <u>How to Configure Network Settings and</u> <u>Licensing on First Boot</u> and <u>Getting Started</u>.

Barracuda Firewall Insights



Figures

- 1. Deploy_Template.png
- 2. Disk_Format.png
- 3. Network_Mapping.png

© Barracuda Networks Inc., 2025 The information contained within this document is confidential and proprietary to Barracuda Networks Inc. No portion of this document may be copied, distributed, publicized or used for other than internal documentary purposes without the written consent of an official representative of Barracuda Networks Inc. All specifications are subject to change without notice. Barracuda Networks Inc. assumes no responsibility for any inaccuracies in this document. Barracuda Networks Inc. reserves the right to change, modify, transfer, or otherwise revise this publication without notice.